
TotalDepth Documentation

Release 0.2.0

Paul Ross

Sep 26, 2017

CONTENTS

| | | |
|----------|------------------------------------------------------------------|------------|
| 1 | Contents | 3 |
| 1.1 | Introduction to TotalDepth | 3 |
| 1.2 | TotalDepth Example Outputs | 3 |
| 1.3 | Installation | 5 |
| 1.4 | Petrophysical File Formats that TotalDepth can Process | 6 |
| 1.5 | Command Line Tools | 7 |
| 1.6 | Usage In a Python Project | 32 |
| 1.7 | Processing LIS Files | 32 |
| 1.8 | Processing LAS Files | 36 |
| 1.9 | TotalDepth Technical Notes | 36 |
| 1.10 | TotalDepth and Software Test | 61 |
| 1.11 | API Reference | 68 |
| 1.12 | A Bag Full of TODO's | 171 |
| 1.13 | Glossary | 172 |
| 1.14 | TotalDepth Licence | 174 |
| 1.15 | Credits | 180 |
| 1.16 | Contributing | 180 |
| 1.17 | History | 182 |
| 1.18 | TotalDepth | 182 |
| 2 | Indices and tables | 185 |
| | Python Module Index | 187 |
| | Index | 189 |

TotalDepth is an Open Source, cross platform, software collection that processes petrophysical data from the oil field such as wireline logs, seismic data and so on.

If you are new here then have a look at some [TotalDepth Example Outputs](#). For more detail see [Introduction to TotalDepth](#).

The [TotalDepth project](#) is currently at **Alpha** version 0.2.0, release 0.2.0. For the licence see [TotalDepth Licence](#).

CONTENTS

1.1 Introduction to TotalDepth

TotalDepth is an Open Source, cross platform, software collection that can process petrophysical data from the oil field such as wireline logs, seismic data and so on.

Conventional, proprietary, software for petrophysical data tends to be expensive to licence, restrictive, slow to develop for and tied to expensive hardware. TotalDepth changes all of that.

TotalDepth is open and cross-platform, and produces results straight to the browser. TotalDepth supports such technologies such as HTML5, AJAX, Software as a Service (SaaS) and Cloud Computing.

1.1.1 Software Technology

For rapid development and performance TotalDepth is written in [Python](#) with performance critical code written in C/C++ or [Cython](#).

TotalDepth was developed using TDD (Test Driven Development) in an agile fashion using *nano-iterations*.

1.2 TotalDepth Example Outputs

This shows some examples of the kind of thing that TotalDepth can do.

1.2.1 Wireline Plots

TotalDepth produced these time honoured plots from LIS and LAS wireline logs in SVG format that can be viewed in most browsers¹.

Plotting from LIS

Some examples of plots generated from LIS79 files:

- A [collection](#) of 9 LIS files where TotalDepth used their internal plot specifications to generate 22 separate plots.
- A [High Resolution Dipmeter](#) plot on a scale of 1:25 with an API header. Fast channel FC0 (red) overlaid on FC1.

¹ There is good SVG support among current browsers such as [Opera](#), [Chrome](#) and [Safari](#). You can find a comparison of browser support for SVG at [Wikipedia](#).

Plotting From LAS

This shows off some examples of plots generated from the Canadian Well Logging Society's LAS formatted files².

Single LAS Plot examples

This shows plots of a single LAS file that has 200 feet of 15 curves. TotalDepth can plot this with, linear and log scales and with an API header:

- Plotted with the [Resistivity 3Track Logarithmic](#) format.
- The same data plotted with the [Triple Combo](#) format.

The original LAS file is [here](#).

A Collection of LAS Plots

Here is a [directory of six LAS files](#) that was used to make 31 individual plots complete with an index that summarises them. For each LAS file the plotting program automatically choose from 29 plot formats the formats that produce useful plots³.

Making LAS Plots

The `PlotLogs.py` command line tool was used with the command:

```
$ python3 PlotLogs.py -A -j4 -r -X 4 Data/ Plot/
```

This searched for LAS files in directory `Data/` with the plots being written in directory `Plot/`.

The following options have been set:

- API headers on the top of each plot: `-A`
- Multiprocessing on with 4 simultaneous jobs: `-j4`
- Recursive search of input directory: `-r`
- Uses any available plot specifications from `LgFormat XML` files which result in 4 curves or more being plotted: `-X 4`

This took around six seconds to compute. More detail on the `PlotLogs.py` is here: [tdplotlogs](#)

1.2.2 LIS Log HTML Summaries

The program `LisToHtml.py` takes LIS file(s) and generates an [HTML summary](#) for each one.

How This HTML was Made

The `LisToHtml.py` command line tool was used with the command:

² Thanks to the [University of Kansas](#) [kgs.ku.edu] for the original data. For these examples that data has been edited or truncated or both.

³ A *useful* plot format is one that can handle at least n curves where n is a number that is specified by the user. If the user specifies 4 then there will be at least 4 curves on each plot.


```
$ python3 LisToHtml.py -k -j4 -r Data/ HTML/
```

This searched for LAS files in directory `Data/` with the files being written to directory `HTML/`.

The following options have been set:

- Keep going as far as possible: `-k`
- Multiprocessing on with 4 simultaneous jobs: `-j4`
- Recursive search of input directory: `-r`

More detail on the `LisToHtml.py` is here: [tdlisthtml](#)

1.3 Installation

1.3.1 Stable release

To install TotalDepth, run this command in your terminal:

```
$ pip install TotalDepth
```

This is the preferred method to install TotalDepth, as it will always install the most recent stable release.

If you don't have `pip` installed, this [Python installation guide](#) can guide you through the process.

1.3.2 From sources

First make a virtual environment in your `<PYTHONVENVS>`, say `~/pyvenvs`:

```
$ python3 -m venv <PYTHONVENVS>/TotalDepth
$ . <PYTHONVENVS>/TotalDepth/bin/activate
(TotalDepth) $
```

Install the dependencies, `numpy` and `Cython`:

```
(TotalDepth) $ pip install numpy
(TotalDepth) $ pip install Cython
```

The sources for TotalDepth can be downloaded from the [Github repo](#).

You can either clone the public repository:

```
(TotalDepth) $ git clone git://github.com/paulross/TotalDepth.git
```

Or download the [tarball](#):

```
(TotalDepth) $ curl -OL https://github.com/paulross/TotalDepth/tarball/master
```

Once you have a copy of the source, you can install it with:

```
(TotalDepth) $ cd TotalDepth
(TotalDepth) $ python setup.py install
```

Install the test dependencies and run TotalDepth's tests:

```
(TotalDepth) $ pip install pytest
(TotalDepth) $ pip install pytest-runner
(TotalDepth) $ python setup.py test
```

1.3.3 Developing with TotalDepth

If you are developing with TotalDepth you need test coverage and documentation tools.

Test Coverage

Install `pytest-cov`:

```
(TotalDepth) $ pip install pytest-cov
```

The most meaningful invocation that eliminates the top level tools is:

```
(TotalDepth) $ pytest --cov=TotalDepth.LAS.core --cov=TotalDepth.LIS.core --
→cov=TotalDepth.RP66.core --cov=TotalDepth.util --cov-report html tests/
```

Documentation

If you want to build the documentation you need to:

```
(TotalDepth) $ pip install Sphinx
(TotalDepth) $ cd docs
(TotalDepth) $ make html
```

1.3.4 System Testing

See *Testing the Plot Package* for comprehensive testing of your installation to see if LIS/LAS files can be written, read and plotted. This pretty much executes all TotalDepth code.

1.3.5 Unit Testing

See *Unit Tests* for more information about testing and unit tests.

1.4 Petrophysical File Formats that TotalDepth can Process

TotalDepth is currently at **Alpha**, release version 0.1.0.

| Format | Support | Since | Notes. |
|-----------------|---------|-------|------------------------------------------------------------------------------------------|
| LIS79 | Full | 0.1.0 | |
| LIS-A | Partial | 0.1.0 | No direct XNAM support. |
| LAS version 1.2 | Full | 0.1.0 | |
| LAS version 2.0 | Full | 0.1.0 | |
| LAS version 3.0 | None | | |
| WellLogML | None | | Absence of good test cases. The format seems to have made little impact on the industry. |
| RP66v1 “DLIS” | Proto. | | Absence of good test cases. |
| RP66v2 “DLIS” | Proto. | | Absence of good test cases. |
| SEG-Y etc. | None | | Use cases? |
| Positioning | None | | Fairly simple, use cases? |

1.5 Command Line Tools

TotalDepth provides a number of tools run from the command line that can analyse and visualise petrophysical data. All the command line tools start with `td`.

1.5.1 TotalDepth Command Line Tools

This describes the command line tools that are available for processing any TotalDepth file.

The tools are located in `TotalDepth/`

Plotting Well Logs

These command line tools plot wireline data.

`tdplotlogs`

Produces SVG plots from LIS and LAS files.

Usage

Usage:

```
usage: tdplotlogs [-h] [--version] [-j JOBS] [-k] [-l LOGLEVEL] [-g] [-r]
                  [-A] [-x LGFORMAT] [-X LGFORMAT_MIN] [-s SCALE]
                  in out
```

Arguments

These are required arguments unless `-h` or `--version` options are specified (in which case no processing is done):

1. The path to the input LAS or LIS file or directory thereof.
2. The path to the output SVG file or directory, any directories will be created as necessary.

Options

| Option | Description |
|---------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>--version</code> | Show program's version number and exit |
| <code>-h</code> , <code>--help</code> | Show this help message and exit. |
| <code>-j JOBS</code> , <code>--jobs=JOBS</code> | Max processes when multiprocessing. Zero uses number of native CPUs [8]. -1 disables multiprocessing. [default: -1] |
| <code>-k</code> , <code>--keep-going</code> | Keep going as far as sensible. [default: False] |
| <code>-l</code> <code>LOGLEVEL</code> , <code>--loglevel=LOGLEVEL</code> | Log Level (debug=10, info=20, warning=30, error=40, critical=50) [default: 20] |
| <code>-g</code> , <code>--glob</code> | File pattern match. [default none] |
| <code>-r</code> , <code>--recursive</code> | Process input recursively. [default: False] |
| <code>-A</code> , <code>--API</code> | Put an API header on each plot. [default: False] |
| <code>-x</code> <code>LGFORMAT</code> , <code>--xml</code> <code>LGFORMAT</code> | Use XML LgFormat UniqueId to use for plotting (additive). Use <code>-x?</code> to see what LgFormats (UniqueID+Description) are available. Use <code>-x??</code> to see what curves each format can plot. See also <code>-X</code> . This is additive so can used multiple times to get multiple plots from the same data. |
| <code>-X</code> <code>LGFORMAT_MIN</code> , <code>--XML</code> <code>LGFORMAT_MIN</code> | Use all available LgFormat XML plots that use <code>LGFORMAT_MIN</code> or more outputs. If <code>-x</code> option present limited by those LgFormats [default: 0] |
| <code>-s SCALE</code> , <code>--scale</code> <code>SCALE</code> | Scale of X axis to use (an integer). This overrides the scale(s) specified in the LgFormat file or FILM table. [default: 0]. |

Examples

LgFormat XML

Using `-x?` to see what formats are available:

```
$ python3 tdplotlogs -x? spam eggs
```

The output is something like:

```
Cmd: tdplotlogs -x? spam eggs
XML LgFormats available: [29]
UniqueId                               Description
-----
ADN_Image_Format                       : ADN Image Log
Azimuthal_Density_3Track.xml           : Azimuthal Density 3Track
```

| | |
|-------------------------------------|------------------------------------------------|
| Azimuthal_Resistivity_3Track.xml | : Azimuthal Resistivity 3Track |
| Blank_3Track_Depth | : Blank 3Track |
| Blank_3Track_Time.xml | : Blank 3Track Time |
| FMI_IMAGE_ALIGNED | : FMI Image Aligned |
| FMI_IMAGE_PROCESSED | : FMI Image Processed |
| Formation_Test | : Formation Test Time |
| HDT | : High Definition Dipmeter |
| Micro_Resistivity_3Track.xml | : Micro Resistivity 3 Track Format |
| Natural_GR_Spectrometry_3Track.xml | : Natural GR Spectrometry 3Track |
| OBMI_IMAGE_EQUAL | : OBMI Image Equalized |
| Porosity_GR_3Track | : Standard Porosity Curves |
| Pulsed_Neutron_3Track.xml | : Pulsed Neutron 3Track |
| Pulsed_Neutron_Time.xml | : Pulsed Neutron Time |
| RAB_Image_Format_Deep | : Resistivity At the Bit Image |
| RAB_Image_Format_Medium | : Resistivity At the Bit Image |
| RAB_Image_Format_Shallow | : Resistivity At the Bit Image |
| RAB_Std_Format | : Resistivity At the Bit |
| Resistivity_3Track_Correlation.xml | : Resistivity Linear Correlation Format |
| Resistivity_3Track_Logrithmic.xml | : Logrithmic Resistivity 3Track |
| Resistivity_Investigation_Image.xml | : AIT Radial Investigation Image |
| Sonic_3Track.xml | : Sonic DT Porosity 3 Track |
| Sonic_PWF4 | : SONIC Packed Waveform 4 |
| Sonic_SPR1_VDL | : SONIC Receiver Array Lower Dipole VDL |
| Sonic_SPR2_VDL | : SONIC Receiver Array Upper Dipole VDL |
| Sonic_SPR3_VDL | : SONIC Receiver Array Stonely VDL |
| Sonic_SPR4_VDL | : SONIC Receiver Array P and S VDL |
| Triple_Combo | : Resistivity Density Neutron GR 3Track Format |

The first column is the UniqueID to be used in identifying plots for the -x option.

Using -x?? to see what formats and what curves would be plotted by each plot specification:

```
$ python3 tdplotlogs -x?? a b
```

The output is something like:

```
Cmd: tdplotlogs -x?? a b
XML LgFormats available: [29]
UniqueID                                     Description
-----
ADN_Image_Format                           : ADN Image Log
  DRHB, GR , GR_RAB, ROBB, ROP5, TNPH
Azimuthal_Density_3Track.xml               : Azimuthal Density 3Track
  BS , DCAL, DRHB, DRHL, DRHO, DRHR, DRHU, DTAB, HDIA, PEB , PEF , PEL
  PER , PEU , RHOB, ROBB, ROBL, ROBR, ROBU, ROP5, RPM , SCN2, SOAB, SOAL
  SOAR, SOAU, SONB, SOXB, VDIA
Azimuthal_Resistivity_3Track.xml           : Azimuthal Resistivity 3Track
  AAI , BS , C1 , C2 , CALI, GR , GRDN_RAB, GRLT_RAB, GRRT_RAB, GRUP_RAB, PCAL,
↪RDBD
  RDBL, RDBR, RDBU, RLA0, RLA1, RLA2, RLA3, RLA4, RLA5, RMBD, RMBL, RMBR
  RMBU, ROP5, RPM , RSBD, RSBL, RSBR, RSBU, SP , TENS
Blank_3Track_Depth                         : Blank 3Track
Blank_3Track_Time.xml                     : Blank 3Track Time
FMI_IMAGE_ALIGNED                         : FMI Image Aligned
  C1 , C2 , GR , HAZIM, P1AZ, SP , TENS
FMI_IMAGE_PROCESSED                       : FMI Image Processed
  C1 , C2 , GR , HAZIM, P1AZ, SP , TENS
Formation_Test                             : Formation Test Time
```

```

    B1TR, BFR1, BQP1, BQP1, BQP1, BQP1, BSG1, POHP
HDT                                     : High Definition Dipmeter
    C1 , C2 , DEVI, FC0 , FC1 , FC2 , FC3 , FC4 , GR , HAZI, P1AZ, RB
Micro_Resistivity_3Track.xml           : Micro Resistivity 3 Track Format
    BMIN, BMNO, BS , CALI, GR , HCAL, HMIN, HMNO, MINV, MLL , MNOR, MSFL
    PROX, RXO , SP , TENS
Natural_GR_Spectrometry_3Track.xml     : Natural GR Spectrometry 3Track
    CGR , PCAL, POTA, ROP5, SGR , SIGM, TENS, THOR, URAN
OBMI_IMAGE_EQUAL                       : OBMI Image Equalized
    C1 , C1_OBMT, C2 , C2_OBMT, GR , HAZIM, OBRA3, OBRB3, OBRC3, OBRD3, P1AZ, P1NO_
↳OBMT
    TENS
Porosity_GR_3Track                     : Standard Porosity Curves
    APDC, APLC, APSC, BS , C1 , C2 , CALI, CALI_CDN, CMFF, CMRP, DPHB, DPHI
    DPHZ, DPOR_CDN, DRHO, ENPH, GR , HCAL, NPHI, NPOR, PCAL, RHOB, RHOZ, ROP5
    SNP , SP , SPHI, TENS, TNPB, TNPH, TNPH_CDN, TPHI
Pulsed_Neutron_3Track.xml              : Pulsed Neutron 3Track
    FBAC, GR , INFD, SIGM, TAU , TCAF, TENS, TPHI, TSCF, TSCN
Pulsed_Neutron_Time.xml                : Pulsed Neutron Time
    FBAC_SL, GR_SL, INFD_SL, SIGM_SL, TAU_SL, TCAF_SL, TENS_SL, TPHI_SL, TSCF_SL,
↳TSCN_SL
RAB_Image_Format_Deep                  : Resistivity At the Bit Image
    GR_RAB, RES_BD, RES_BM, RES_BS, RES_RING, ROP5
RAB_Image_Format_Medium                : Resistivity At the Bit Image
    GR_RAB, RES_BD, RES_BM, RES_BS, RES_RING, ROP5
RAB_Image_Format_Shallow               : Resistivity At the Bit Image
    GR_RAB, RES_BD, RES_BM, RES_BS, RES_RING, ROP5
RAB_Std_Format                         : Resistivity At the Bit
    AAI , BDAV, BDM3, BMAV, BMM2, BSAV, BSM1, BTAB, CALI, DEVI, GR_RAB, HAZI
    OBIT, RBIT, RING, ROP5, RPM , RTAB
Resistivity_3Track_Correlation.xml      : Resistivity Linear Correlation Format
    AHT20, AHT60, AHT90, ATR , BS , CALI, CATR, CILD, CLLD, GR , HCAL, ILD
    ILM , LLD , LLS , MSFL, PCAL, PSR , RLA0, ROP5, RT , RXO , SFL , SP
    TENS
Resistivity_3Track_Logrithmic.xml       : Logrithmic Resistivity 3Track
    A22H, A34H, AHF10, AHF20, AHF30, AHF60, AHF90, AHO10, AHO20, AHO30, AHO60, AHO90
    AHT10, AHT20, AHT30, AHT60, AHT90, ATR , BS , CALI, GR , HCAL, ILD , ILM
    LLD , LLM , MSFL, P16H_RT, P28H_RT, P34H_RT, PCAL, PSR , RLA0, RLA1, RLA2, RLA3
    RLA4, RLA5, ROP5, RXO , SFL , SP , TENS
Resistivity_Investigation_Image.xml     : AIT Radial Investigation Image
    AHT10, AHT20, AHT30, AHT60, AHT90, BS , GR , HCAL, SP
Sonic_3Track.xml                       : Sonic DT Porosity 3 Track
    BS , CALI, DT , DT0S, DT1R, DT2 , DT2R, DT4S, DTBC, DTCO, DTCU, DTL
    DTLF, DTLN, DTR2, DTR5, DTRA, DTRS, DTSH, DTSM, DTST, DTTA, GR , HCAL
    PCAL, ROP5, SP , SPHI, TENS
Sonic_PWF4                             : SONIC Packed Waveform 4
    CALI, DT1 , DT2 , DTCO, DTSM, DTST, GR , HCAL, TENS
Sonic_SPR1_VDL                         : SONIC Receiver Array Lower Dipole VDL
    CALI, DT1 , DT1 , DT2 , DTCO, DTSM, DTST, GR , HCAL, TENS
Sonic_SPR2_VDL                         : SONIC Receiver Array Upper Dipole VDL
    CALI, DT1 , DT2 , DT2 , DTCO, DTSM, DTST, GR , HCAL, TENS
Sonic_SPR3_VDL                         : SONIC Receiver Array Stonely VDL
    CALI, DT1 , DT2 , DT3R, DTCO, DTSM, DTST, GR , HCAL, TENS
Sonic_SPR4_VDL                         : SONIC Receiver Array P and S VDL
    CALI, DT1 , DT2 , DTCO, DTRP, DTRS, DTSM, DTST, GR , HCAL, TENS
Triple_Combo                           : Resistivity Density Neutron GR 3Track Format
    AHT10, AHT20, AHT30, AHT60, AHT90, APDC, APLC, APSC, ATR , BS , C1 , C2
    CALI, CMFF, CMRP, DPHB, DPHI, DPHZ, DPOR_CDN, DSOZ, ENPH, GR , HCAL, HMIN

```

```
HMNO, ILD , ILM , LLD , LLM , MSFL, NPFI, NPOR, PCAL, PEFZ, PSR , RLA0
RLA1, RLA2, RLA3, RLA4, RLA5, ROP5, RSOZ, RXO , RXOZ, SFL , SNP , SP
SPFI, TENS, TNPB, TNPB, TNPB_CDN, TPHI
```

Plotting Logs

Here is an example of plotting LIS and LAS files in directory `in/` with the plots in directory `out/`. The following options have been invoked:

- API headers on the top of each plot: `-A`
- Multiprocessing on with 4 simultaneous jobs: `-j4`
- Recursive search of input directory: `-r`
- Uses any available plot specifications from LgFormat XML files which result in 4 curves or more being plotted: `-X 4`

The command line is:

```
$ python3 tdplotlogs -A -j4 -r -X 4 in/ out/
```

First `tdplotlogs` echos the command:

```
Cmd: tdplotlogs -A -j4 -r -X 4 in/ out/
```

When complete `tdplotlogs` writes out a summary, first the number of files read (output is wrapped here with “ for clarity):

```
plotLogInfo PlotLogInfo <__main__.PlotLogInfo object at 0x101e0da90> \
  Files=23 \
  Bytes=10648531 \
  LogPasses=23 \
  Plots=8 \
  Curve points=229991
```

Then as summary of each plot in detail (output is wrapped here with “ for clarity):

```
('in/1003578128.las', \
  0, \
  'Natural_GR_Spectrometry_3Track.xml', \
  IndexTableValue( \
    scale=100, \
    evFirst='800.5 (FEET)', \
    evLast='3019.5 (FEET)', \
    evInterval='2219.0 (FEET)', \
    curves='CGR_2, POTA, SGR_1, TENS_16, THOR, URAN', \
    numPoints=26213, \
    outPath='out//1003578128.las_0000_Natural_GR_Spectrometry_3Track.xml.
→svg' \
  )
)
('in/1003578128.las', \
  0, \
  'Porosity_GR_3Track', \
  IndexTableValue( \
    scale=100, \
    evFirst='800.5 (FEET)', \
```

```
        evLast='3019.5 (FEET)', \
        evInterval='2219.0 (FEET)', \
        curves='Cali, DRHO, DensityPorosity, GammaRay, NeutronPorosity,
↳OLDESTNeutronPorosity, OLDNeutronPorosity, RHOB, SP, SonicPorosity, Tension', \
        numPoints=46170, \
        outPath='out//1003578128.las_0000_Porosity_GR_3Track.svg' \
    )
)

... 8<----- Snip ----->8

('in/1006346987.las', \
 0, 'Sonic_3Track.xml', \
 IndexTableValue(
     scale=100, \
     evFirst='4597.5 (FEET)', \
     evLast='5799.5 (FEET)', \
     evInterval='1202.0 (FEET)', \
     curves='Caliper, DT, DTL_DDBHC, GammaRay, SonicPorosity, TENSION', \
     numPoints=14430, \
     outPath='out//1006346987.las_0000_Sonic_3Track.xml.svg' \
 )
)
```

The fields in each tuple are:

- Input file name.
- LogPass number in the file. For example “Repeat Section” might be 0 and “Main Log” 1.
- LgFormat used for the plot (several plots may be generated from one LogPass).
- **An IndexTableValue object (used to generate the index.html file) that has the following fields:**
 - Plot scale as an integer.
 - First reading and units as an Engineering Value.
 - Last reading and units as an Engineering Value.
 - Log interval and units as an Engineering Value.
 - List of curve names plotted.
 - Total number of data points plotted.
 - The output file.

Finally the total number of curve feet plotted and the time it took:

```
Interval*curves: EngVal: 121020.000 (FEET)
CPU time =      0.043 (S)
Exec. time =    25.119 (S)
Bye, bye!
```

In this case (under Unix) the “CPU Time” is the cumulative amount of CPU time used. As we are using multiprocessing it is the CPU time of the parent process which is very small since it just invokes child processes. The Exec. time is the wall clock time between starting and finishing `tdplotlogs`.


In the output directory will be an `index.html` file that has a table with the fields that duplicate those on the command line output. It looks like this:

○ ○ ○
LIS plots in SVG

PlotLogPasses: ../../TDTestData/LAS/uz_small/

| Input | Pass | Film | Scale | From | To | Interval | Curves | Points | Plot |
|----------------|------|------------------------------------|-------|------------------|------------------|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------|--------|----------------------------------------------------------------------------|
| 1003578128.las | 0 | Natural_GR_Spectrometry_3Track.xml | 100 | 800.5 (FEET) | 3019.5 (FEET) | 2219.0 (FEET) | CGR_2, POTA, SGR_1, TENS_16, THOR, URAN | 26213 | 1003578128.las_0000 Natural_GR_Spectrometry_3Track.xml.svg |
| | | Porosity_GR_3Track | 100 | 800.5 (FEET) | 3019.5 (FEET) | 2219.0 (FEET) | Cali, DRHO, DensityPorosity, GammaRay, NeutronPorosity, OLDESTNeutronPorosity, OLDNeutronPorosity, RHOB, SP, SonicPorosity, Tension | 48170 | 1003578128.las_0000 Porosity_GR_3Track.svg |
| | | Resistivity_3Track_Correlation.xml | 100 | 800.5 (FEET) | 3019.5 (FEET) | 2219.0 (FEET) | CALJ_8, CILD, GR_9, SP_10, TENS_6 | 22012 | 1003578128.las_0000 Resistivity_3Track_Correlation.xml.svg |
| | | Resistivity_3Track_Logrithmic.xml | 100 | 800.5 (FEET) | 3019.5 (FEET) | 2219.0 (FEET) | CALJ_8, GR_9, ILD, ILM, SFL, SP_10, TENS_6 | 30878 | 1003578128.las_0000 Resistivity_3Track_Logrithmic.xml.svg |
| | | Sonic_3Track.xml | 100 | 800.5 (FEET) | 3019.5 (FEET) | 2219.0 (FEET) | Caliper, DTLF, DDBHC, DTLN, DDBHC, GammaRay, SP, SonicPorosity, TENSION | 24935 | 1003578128.las_0000 Sonic_3Track.xml.svg |
| | | Triple_Combo | 100 | 800.5 (FEET) | 3019.5 (FEET) | 2219.0 (FEET) | Cali, DensityPorosity, GammaRay, ILD, ILM, NeutronPorosity, OLDESTNeutronPorosity, OLDNeutronPorosity, SFL, SP, SonicPorosity, Tension | 50755 | 1003578128.las_0000 Triple_Combo.svg |
| 1003409986.las | 0 | Porosity_GR_3Track | 100 | 4592.0 (FEET) | 5808.0 (FEET) | 1216.0 (FEET) | Cali, DRHO, DensityPorosity, GammaRay, OLDESTNeutronPorosity, RHOB | 14598 | 1003409986.las_0000 Porosity_GR_3Track.svg |
| 1003409987.las | 0 | Sonic_3Track.xml | 100 | 4597.5 (FEET) | 5799.5 (FEET) | 1202.0 (FEET) | Caliper, DT, DTL, DDBHC, GammaRay, SonicPorosity, TENSION | 14430 | 1003409987.las_0000 Sonic_3Track.xml.svg |

The links in the last column are to the SVG plots. Her is a screen shot of one:



Sample Plots

Here is an actual plot from a [LAS file](#) and there are many more examples here: [Wireline Plots](#).

1.5.2 LIS Command Line Tools

This describes the command line tools that are available for processing LIS files.

| Tool Name | Description |
|---------------------|-------------------------------------------------|
| tdlisdetif | Removes TIF markers from a LIS file. |
| tdlisdumpframeset | Writes out the frame values as a CSV file. |
| tdlisindex | Indexes a LIS file. |
| tdlisplotlogpasses | Plots the log data as SVG pages. |
| tdlisscanlogidata | Scans the logical data. |
| tdlisscanlogirecord | Scans all Logical records. |
| tdlisscanphysrec | Scans all the Physical Records. |
| tdlistablehistogram | Analyses the contents of table Logical Records. |
| tdlistohtml | Generates a HTML page about the LIS file. |
| tdplotlogs | Plots logs as SVG files. |

Scanning LIS Files

These command line tools scan LIS files without changing them.

`tdlisscanphysrec`

Scans a LIS79 file and reports the Physical Record structure.

Arguments

One argument that will be treated as a path to a LIS file.

Options

| Option | Description |
|---------------------------------------------------------------|--------------------------------------------------------------------------------|
| <code>--version</code> | Show program's version number and exit |
| <code>-h, --help</code> | Show this help message and exit. |
| <code>-k, --keep-going</code> | Keep going as far as sensible. [default: False] |
| <code>-l LOGLEVEL,</code> <code>--loglevel=LOGLEVEL</code> | Log Level (debug=10, info=20, warning=30, error=40, critical=50) [default: 20] |

Examples

Example of scanning a non-TIF encoded file:

```
$ ``tdlisscanphysrec`` LIS.lis
Cmd: ScanPhysRec.py LIS.lis
PR:      tell()  Length   Attr  LD_len  RecNum  FilNum  ChkSum   LR Attr [Total LD]
-----
PR: 0x      0      62  0x  0      58  -----  -----  -----  0x80 0x00 [      58]
PR: 0x     3e    1024  0x  1    1020  -----  -----  -----  0x22 0x00
PR: 0x    43e    1024  0x  3    1020  -----  -----  -----  + --  --
PR: 0x    83e    1024  0x  3    1020  -----  -----  -----  + --  --
PR: 0x    c3e    1024  0x  3    1020  -----  -----  -----  + --  --
PR: 0x   103e    1024  0x  3    1020  -----  -----  -----  + --  --
PR: 0x   143e    1024  0x  3    1020  -----  -----  -----  + --  --
```

```

PR: 0x 183e 1024 0x 3 1020 ----- + -- --
PR: 0x 1c3e 1024 0x 3 1020 ----- + -- --
PR: 0x 203e 34 0x 2 30 ----- + -- -- [ 8190]
PR: 0x 2060 304 0x 0 300 ----- 0x40 0x00 [ 300]
PR: 0x 2190 1014 0x 0 1010 ----- 0x00 0x00 [ 1010]
PR: 0x 2586 1014 0x 0 1010 ----- 0x00 0x00 [ 1010]
PR: 0x 297c 1014 0x 0 1010 ----- 0x00 0x00 [ 1010]
PR: 0x 2d72 1014 0x 0 1010 ----- 0x00 0x00 [ 1010]
PR: 0x 3168 1014 0x 0 1010 ----- 0x00 0x00 [ 1010]
PR: 0x 355e 1014 0x 0 1010 ----- 0x00 0x00 [ 1010]
PR: 0x 3954 1014 0x 0 1010 ----- 0x00 0x00 [ 1010]
PR: 0x 3d4a 1014 0x 0 1010 ----- 0x00 0x00 [ 1010]
PR: 0x 4140 942 0x 0 938 ----- 0x00 0x00 [ 938]
PR: 0x 44ee 62 0x 0 58 ----- 0x81 0x00 [ 58]
PR: EOF
----- EOF -----
PR Count: 21
Histogram of Physical Record lengths:
Bytes
  34 [1] | ++++++++
  62 [2] | ++++++
 304 [1] | ++++++++
 942 [1] | ++++++++
1014 [8] | _
↪+++++
1024 [8] | _
↪+++++
CPU time = 0.001 (S)
Bye, bye!

```

First `tdlisscanphysrec echo`'s the command line then it scans the Physical Records and writes out a table that has the following columns:

| Heading | Description |
|-------------------------|--------------------------------------------------------------------------------------------------------------|
| <code>tell()</code> | The file position of the start of the Physical Record as a hex integer. |
| <code>Length</code> | The length of the Physical Record as a decimal integer. |
| <code>Attr</code> | The Physical Record Header attributes as a hex integer. |
| <code>LD_len</code> | The length of the logical data payload contained in this Physical Record. |
| <code>RecNum</code> | A record number from the Physical Record trailer if present, otherwise: ----- |
| <code>FilNum</code> | A file number from the Physical Record trailer if present, otherwise: ----- |
| <code>ChkSum</code> | A checksum from the Physical Record trailer if present, otherwise: ----- |
| <code>LR</code> | Logical Record type from the Logical Record Header as a hex integer. |
| <code>Attr</code> | Logical Record attributes from the Logical Record Header as a hex integer. This is (almost?) always 0x00 |
| <code>[Total LD]</code> | The total length of the logical data in the Logical Record if a terminator Physical Record, otherwise blank. |

This is followed by an ASCII histogram of the lengths of all Physical Records with the following columns:

1. The size in bytes.
2. The frequency count.
3. A series of + that is proportionate to the frequency count.

If TIF markers are detected then the output adds TIF columns thus:

| TIF | ? | : | Type | Back | Next | PR: | tell() | Length | Attr | LD_ |
|-------------------|--------|--------|--------|---------|------------|------|--------|--------|--------|------|
| →len | RecNum | FilNum | ChkSum | LR Attr | [Total LD] | | | | | |
| ----- start ----- | | | | | | | | | | |
| → | | | | | | | | | | |
| TIF | True | >: | 0x | 0 | 0x | 0 | 0x | 4a | PR: 0x | 0 |
| →58 | ----- | ----- | ----- | 0x80 | 0x00 | [| 58] | | | ┌ |
| TIF | True | >: | 0x | 0 | 0x | 0 | 0x | 456 | PR: 0x | 4a |
| →1020 | ----- | ----- | ----- | 0x22 | 0x00 | | | | | ┌ |
| TIF | True | >: | 0x | 0 | 0x | 4a | 0x | 862 | PR: 0x | 456 |
| →1020 | ----- | ----- | ----- | + | -- | -- | | | | ┌ |
| TIF | True | >: | 0x | 0 | 0x | 456 | 0x | c6e | PR: 0x | 862 |
| →1020 | ----- | ----- | ----- | + | -- | -- | | | | ┌ |
| TIF | True | >: | 0x | 0 | 0x | 862 | 0x | 107a | PR: 0x | c6e |
| →1020 | ----- | ----- | ----- | + | -- | -- | | | | ┌ |
| TIF | True | >: | 0x | 0 | 0x | c6e | 0x | 1486 | PR: 0x | 107a |
| →1020 | ----- | ----- | ----- | + | -- | -- | | | | ┌ |
| TIF | True | >: | 0x | 0 | 0x | 107a | 0x | 1892 | PR: 0x | 1486 |
| →1020 | ----- | ----- | ----- | + | -- | -- | | | | ┌ |
| TIF | True | >: | 0x | 0 | 0x | 1486 | 0x | 1c9e | PR: 0x | 1892 |
| →1020 | ----- | ----- | ----- | + | -- | -- | | | | ┌ |
| TIF | True | >: | 0x | 0 | 0x | 1892 | 0x | 20aa | PR: 0x | 1c9e |
| →1020 | ----- | ----- | ----- | + | -- | -- | | | | ┌ |
| TIF | True | >: | 0x | 0 | 0x | 1c9e | 0x | 20ec | PR: 0x | 20aa |
| →50 | ----- | ----- | ----- | + | -- | -- | [| 8210] | | ┌ |

The additional columns are:

| Heading | Description |
|---------|----------------------------------------------------------------|
| ? | ? |
| Type | TIF marker type, 0 for in-file record, 1 for EOF. |
| Back | The file position of the precious TIF marker as a hex integer. |
| Next | The file position of the next TIF marker as a hex integer. |

tdlisscanlogirecord

Scans a LIS79 file and reports the Logical Record structure.

Arguments

One argument that will be treated as a path to a LIS file.

Options

| Option | Description |
|-------------------------------------|--------------------------------------------------------------------------------|
| --version | Show program's version number and exit |
| -h, --help | Show this help message and exit. |
| -k, --keep-going | Keep going as far as sensible. [default: False] |
| -l LOGLEVEL, --loglevel=LOGLEVEL | Log Level (debug=10, info=20, warning=30, error=40, critical=50) [default: 20] |
| -v, --verbose | Verbose output, this outputs a representation of table data and DFSRs. |

Examples

Example of scanning a LIS file:

```
$ tdlisscanlogirecord RW.lis
Cmd: ScanLogiRec.py RW.lis
0x00000000 <TotalDepth.LIS.core.LogiRec.LrFileHeadRead object at 0x1007981d0>: "File_
↳header"
2012-02-08 17:43:45,078 WARNING LrTableRead(): Discarding duplicate row b'BS7 ' in_
↳table b'CONS'
2012-02-08 17:43:45,087 WARNING LrTableRead.__init__(): Tell: 0x4a LD index: 0x32_
↳Error: FileRead.unpack(): Bytes: b'\x00' not enough for struct that needs: 12 bytes.
0x0000004a <TotalDepth.LIS.core.LogiRec.LrTableRead object at 0x100798210>: "Well_
↳site data"
0x000020ec <TotalDepth.LIS.core.LogiRec.LrDFSRRead object at 0x1007981d0>: "Data_
↳format specification record"
0x0006141c <TotalDepth.LIS.core.LogiRec.LrFileTailRead object at 0x10058e7d0>: "File_
↳trailer"
0x00061466 <TotalDepth.LIS.core.LogiRec.LrFileHeadRead object at 0x10058e850>: "File_
↳header"
2012-02-08 17:43:45,103 WARNING LrTableRead(): Discarding duplicate row b'BS7 ' in_
↳table b'CONS'
0x000614b0 <TotalDepth.LIS.core.LogiRec.LrTableRead object at 0x10058e7d0>: "Well_
↳site data"
0x0006353e <TotalDepth.LIS.core.LogiRec.LrDFSRRead object at 0x10058e850>: "Data_
↳format specification record"
0x00065a44 <TotalDepth.LIS.core.LogiRec.LrFileTailRead object at 0x10058e850>: "File_
↳trailer"
0x00065a8e <TotalDepth.LIS.core.LogiRec.LrFileHeadRead object at 0x10058e7d0>: "File_
↳header"
2012-02-08 17:43:45,116 WARNING LrTableRead(): Discarding duplicate row b'BS7 ' in_
↳table b'CONS'
2012-02-08 17:43:45,124 WARNING LrTableRead.__init__(): Tell: 0x65ad8 LD index: 0x32_
↳Error: FileRead.unpack(): Bytes: b'\x00' not enough for struct that needs: 12 bytes.
0x00065ad8 <TotalDepth.LIS.core.LogiRec.LrTableRead object at 0x10058e850>: "Well_
↳site data"
0x00067b7a <TotalDepth.LIS.core.LogiRec.LrDFSRRead object at 0x10058e7d0>: "Data_
↳format specification record"
0x000d2c44 <TotalDepth.LIS.core.LogiRec.LrFileTailRead object at 0x10058e7d0>: "File_
↳trailer"
CPU time = 0.064 (S)
Bye, bye!
```

tdlisscanlogidata

Scans a LIS79 file and reports the Logical Record structure.

Arguments

One argument that will be treated as a path to a LIS file.

Options

| Option | Description |
|-------------------------------------|------------------------------------------------------------------------------------|
| --version | Show program's version number and exit |
| -h, --help | Show this help message and exit. |
| -k, --keep-going | Keep going as far as sensible. [default: False] |
| -d DUMP, --dump=DUMP | Dump complete data at these integer positions (ws separated, hex/dec). [default:] |
| -l LOGLEVEL, --loglevel=LOGLEVEL | Log Level (debug=10, info=20, warning=30, error=40, critical=50) [default: 20] |
| -v, --verbose | Verbose output, this outputs a representation of table data and DFSRs. |

Examples

Example of scanning a LIS file:

```
$ ``tdlisscanlogidata`` LIS.lis
Cmd: ScanLogiData.py LIS.lis
Offset      Length  Type  Logical Data
0x00000000      58    128  b'\x80\x00RUN1R .S01\x00\x00DAT2TF'...
0x0000003E     8190    34  b'"'\x00IA\x04\x00TYPE  CONS\x00A\x04\x00MNEM  HI'...'
0x00002060      300    64  b
↳ '@\x00\x01\x02O\x00\x00\x02O\x00\x00\x03\x04I\x00\x00\x00\x18\x04\x02O\x00\x01\x08\x04D?
↳ N\x07_\t'...'
0x00002190     1010     0  b"\x00\x00F@
↳ '\xde\xbe76\xfb@\xd6\x1a\xc0@\xd0\xdc\xc7D\xe0\xa6P\xba\x83\x18\x00F@&\xa6\xbe-'...'
0x00002586     1010     0  b'\x00\x00E\xff\xe9S\xbe:\x1f\x82@\xfe
↳ %\xc9@\xf7\xd5\xb7EA\x90\xda\xba\x83\x18\x00E\xff\xe6\xe3\xbe\x8a'...'
0x0000297C     1010     0  b'\x00\x00E\xff\x82\xea\xbe-
↳ \xe1\xa8@\xd83\xb6@\xf0\xf0fET\x149D\xc8\x08\xc5E\xff\x80y\xbe-'...'
0x00002D72     1010     0  b
↳ '\x00\x00E\xff\x1c\x80\xbd\xba\x7f\x19@\xc4\xbf\xe8@y\x0b\x3E\xc0\x08\x03D\xd5\xednE\xff\x1a\x10\
↳ '...'
0x00003168     1010     0  b
↳ '\x00\x00E\xfe\xb6\x16\xbe\x12\xde\xf0@\xcbl\xe7@zF\xc2Ew\xba/
↳ D\xd0\xca\xd9E\xfe\xb3\xa6\xbe\x17'...'
0x0000355E     1010     0  b
↳ '\x00\x00E\xfeO\xac\xbe40\x85@\xcc4\x8d@of\xd9E\xc1F\xd8D\xd4\xaa+E\xfeM<\xbe6'...'
0x00003954     1010     0  b"\x00\x00E\xfd\xe9C\xbd\xb2\x19\xf0\xba\x83\x18\x00AK'
↳ %D\xed\x9d\xbdD\xd0\x17RE\xfd\xe6\xd3\xbd\xab"...'
0x00003D4A     1010     0  b
↳ '\x00\x00E\xfd\x82\xd9\xba\x83\x18\x00\xba\x83\x18\x00\xba\x83\x18\x00\xba\x83\x18\x00D\xd0\xad\xfd
↳ '...'
0x00004140      938     0  b
↳ '\x00\x00E\xfd\x1co\xba\x83\x18\x00\xba\x83\x18\x00\xba\x83\x18\x00\xba\x83\x18\x00D\xd8\x8c\xb5E\
↳ '...'
0x000044EE      58     0  b'\x81\x00RUN1R .S01\x00\x00DAT2TF'...
Histogram of Logical Data lengths:
Bytes
  58 [1] | ++++++++
 300 [1] | ++++++++
 938 [1] | ++++++++
1010 [8] | _
↳ ++++++++
8190 [1] | ++++++++
```

```
Histogram of Logical Record types:
 0 [9] |_
↪+++++
34 [1] | +++++
64 [1] | +++++
128 [1] | +++++
CPU time =    0.001 (S)
Bye, bye!
```

First `tdlisscanlogidata` echo's the command line then it scans the file an writes out a table that has the following columns:

| Heading | Description |
|--------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Offset | The file position of the start of the Physical Record as a hex integer. |
| Length | The length of the Logical Record as a decimal integer. |
| Type | The Logical Record type as a decimal integer. |
| Logical Data | The logical data payload. Only the first 32 bytes are shown. . . . is shown if the payload is longer than 32 bytes. If the verbose or dump options are given then all bytes are shown. |

This is followed by an ASCII histogram of the lengths of all logical data with the following columns:

- 1. The size in bytes.
- 2. The frequency count.
- 3. A series of + that is proportionate to the frequency count.

This is followed by an ASCII histogram of the lengths of all Logical Record types with the following columns:

- 1. The size in bytes.
- 2. The frequency count.
- 3. A series of + that is proportionate to the frequency count.

Using the `-d` option expands the output when the file position value matches. So given the above then adding `-d 0x44EE` changes this:

```
...
0x000044EE      58      0  b'\x81\x00RUN1R .S01\x00\x00DAT2TF'      '...'
...
```

To this:

```
...
0x000044EE      58      0  b'\x81\x00RUN1R .S01\x00\x00DAT2TF'      \x00_
↪1024\x00\x00\x00\x00\x00\x00\x00\x00\x00\x00\x00\x00\x00\x00\x00\x00'
...
```

Extracting Data from LIS

`tdlisdumpframeset`

Reads a LIS file and writes out tab separated values of each frame.

Arguments

1. The path to the LIS file.

Options

| Option | Description |
|-------------------------------------|--------------------------------------------------------------------------------|
| --version | Show program's version number and exit |
| -h, --help | Show this help message and exit. |
| -k, --keep-going | Keep going as far as sensible. [default: False] |
| -l LOGLEVEL, --loglevel=LOGLEVEL | Log Level (debug=10, info=20, warning=30, error=40, critical=50) [default: 20] |
| -s, --summary | Display summary only [default: False]. |

Examples

```
$ ``tdlisdumpframeset`` LIS.lis
Cmd: DumpFrameSet.py LIS.lis
2012-02-09 08:41:38,372 INFO      Index.indexFile(): LIS.lis
<TotalDepth.LIS.core.LogPass.LogPass object at 0x101a0c510>
b'DEPT' [b'M'  '] b'SP'  '[b'MV'  '] b'SN'  '[b'OHMM'] b'ILD' '[b'OHMM'] b'CILD
↳ [b'MMHO'] b'DT' '[b'US/M']
2052.98 -4.54908      1.34538 1.26348 386.599 -999.25
2052.83 -5.1372      1.36062 1.29521 500.511 -999.25
2052.68 -6.66747      1.38543 1.45786 595.623 -999.25
2052.53 -6.69616      1.43226 1.61085 592.447 -999.25
2052.37 -4.93782      1.51647 1.6622  590.846 -999.25
2052.22 -4.38823      1.66883 1.70584 586.092 -999.25
2052.07 -4.70347      1.8102  1.70607 577.873 -999.25
...
1996.44 -999.25      -999.25 -999.25 -999.25 -999.25
1996.29 -999.25      -999.25 -999.25 -999.25 -999.25
1996.14 -999.25      -999.25 -999.25 -999.25 -999.25
1995.99 -999.25      -999.25 -999.25 -999.25 -999.25

Sc Name          Count      Min      Mean      Max Std Dev.      --      ==      ++
↳ Bias      Drift Activity
DEPT [M  ]          375      2e+03 2.02e+03 2.05e+03      16.5      374      0      0
↳ 1      -0.152 0.000144
SP  [MV  ]          262      -13.7   -5.67   -0.769      2.66      124      0      137
↳ -0.0498  0.0144  0.678
SN  [OHMM]          252      0.866    1.36    1.98      0.277      123      0      128
↳ -0.0199 -0.000719  0.0425
ILD [OHMM]          253      0.361    1.31    2.35      0.412      95      0      157
↳ -0.246  0.00429  0.134
CILD [MMHO]         253      387      787 1.75e+03      236      130      0      122
↳ 0.0317  0.205  0.101
DT  [US/M]          292      133      320     460      42.5      139      0      152
↳ -0.0447 -0.451  0.106
CPU time = 0.047 (S)
Bye, bye!
```

The summary table at the end has the following columns:

| Heading | Description |
|----------|----------------------------------------------------------------|
| Sc Name | The sub-channel name and units of measure. |
| Count | The number of non-null values. |
| Min | Minimum value. |
| Mean | Arithmetic mean of values. |
| Max | Maximum value. |
| Std Dev. | Standard deviation of values. |
| -- | Number of values that are a decrease over the previous value. |
| == | Number of values that are equal to the previous value. |
| ++ | Number of values that are an increase over the previous value. |
| Bias | (-- - ++) / total |
| Drift | (last value - first value) / number of values |
| Activity | The RMS exponent change. |

tdlistohtml

Generates HTML from input LIS file or directory to an output destination.

Arguments

1. The path to the input LIS file or directory.
2. The path to the output file or directory, any directories will be created as necessary.

Options

| Option | Description |
|----------------------------------|---------------------------------------------------------------------------------------------------------------------|
| --version | Show program's version number and exit |
| -h, --help | Show this help message and exit. |
| -g, --glob | File pattern match. [default none] |
| -j JOBS, --jobs=JOBS | Max processes when multiprocessing. Zero uses number of native CPUs [8]. -1 disables multiprocessing. [default: -1] |
| -k, --keep-going | Keep going as far as sensible. [default: False] |
| -l LOGLEVEL, --loglevel=LOGLEVEL | Log Level (debug=10, info=20, warning=30, error=40, critical=50) [default: 20] |
| -v, --verbose | Verbose output, this outputs a representation of table data and DFSRs. |
| -r, --recursive | Process input recursively. [default: False] |

Examples

Command to process a directory of LIS:

```
$ ``tdlistohtml`` Simple LIS_plot/Simple_00
```


Output:

```
Cmd: ``tdlisttohtml`` Simple LIS_plot/Simple_00
plotLogInfo:
FileInfo: "Simple/LIS.lis" -> "LIS_plot/Simple_00/LIS.lis.html" 17 (kb) LR count=4_
↳t=0.070
FileInfo: "Simple/RW.lis" -> "LIS_plot/Simple_00/RW.lis.html" 843 (kb) LR count=12_
↳t=3.206
FileInfo: "Simple/RW_No_TIF.lis" -> "LIS_plot/Simple_00/RW_No_TIF.lis.html" 833 (kb)_
↳LR count=12 t=3.200
CPU time = 6.568 (S)
Exec. time = 6.568 (S)
Bye, bye!
```

For each file the output lists:

- Input file.
- Output HTML file.
- File size.
- Count of Logical Records.
- Execution time.

In the output directory there will be an index.html file, for example:



| LIS File | Size (MB) | Record Entries | CPU Time (s) | Rate (MB/s) |
|--------------------------|-----------|----------------|--------------|-------------|
| 2851.S1 | 0.026 | 14 | 0.117 | 0.219 |
| 2851.S2 | 0.176 | 11 | 1.110 | 0.159 |
| 2851.S3 | 0.161 | 11 | 1.012 | 0.159 |
| 2851.S4 | 0.052 | 11 | 0.310 | 0.169 |
| 2851.S5 | 0.058 | 11 | 0.346 | 0.169 |
| 2851.S6 | 0.028 | 11 | 0.149 | 0.186 |
| 2851.S7 | 0.236 | 11 | 1.504 | 0.157 |
| 2951.S1 | 0.182 | 18 | 0.659 | 0.277 |
| 2951.S2 | 0.097 | 15 | 0.367 | 0.264 |
| 2953.S10 | 0.041 | 9 | 0.230 | 0.179 |
| 2953.S12 | 0.016 | 10 | 0.068 | 0.236 |
| 2953.S13 | 0.084 | 10 | 0.582 | 0.145 |
| 2953.S14 | 0.031 | 19 | 0.136 | 0.227 |
| 2953.S15 | 0.015 | 11 | 0.065 | 0.232 |
| 2953.S16 | 0.071 | 11 | 0.484 | 0.148 |
| 2953.S17 | 0.031 | 17 | 0.133 | 0.233 |
| 2953.S18 | 0.015 | 10 | 0.065 | 0.234 |
| 2953.S19 | 0.074 | 10 | 0.437 | 0.169 |
| 2955.S1 | 0.028 | 10 | 0.117 | 0.238 |
| 2955.S2 | 1.487 | 12 | 9.463 | 0.157 |
| Totals | 2.910 | 242 | 17.352 | 0.168 |

The columns are:

- The name of the LIS file.
- The size of the LIS file.

- Count of Logical Records.
- Execution time.
- Processing rate.

In the linked HTML file is a summary of the content of the LIS file.

The Log Pass merits several entries, the first summarises the frame shape and the shape of each channel, for example:

LIS analysis of ../../../../TDTestData/LIS/pLogicTestData_med/LIS/13615.S3

Overview — Documentation Apple Yahoo! Google Maps YouTube Wikipedia News (225) Popular

Log Pass at 0x3f6

Frame Information

| | Value |
|--------------------|-----------|
| Frame length | 118 bytes |
| Number of Channels | 8 |
| Indirect X size | 4 bytes |

Channels

RHDT, P1AZ (DEG), DEVI (DEG), HAZI (DEG), C1 (INCH), C2 (INCH), FEP (VOLT), RB (DEG)

| Name | Service ID | Service Order | Units | API | File | Size | Rep Code | Sub-channels | Values per frame | Shape [sc, sa, bu] |
|------|------------|---------------|-------|-------------|------|------|----------|--------------|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| RHDT | HDT | | | 00-000-00-0 | 3 | 90 | 234 | 15 | 90 | (0, 16, 1), (1, 16, 1), (2, 16, 1), (3, 16, 1), (4, 16, 1), (5, 1, 1), (6, 1, 1), (7, 1, 1), (8, 1, 1), (9, 1, 1), (10, 1, 1), (11, 1, 1), (12, 1, 1), (13, 1, 1), (14, 1, 1) |
| P1AZ | HDT | | DEG | 00-000-00-0 | 3 | 4 | 68 | 1 | 1 | (0, 1, 1) |
| DEVI | HDT | | DEG | 00-000-00-0 | 3 | 4 | 68 | 1 | 1 | (0, 1, 1) |
| HAZI | HDT | | DEG | 00-000-00-0 | 3 | 4 | 68 | 1 | 1 | (0, 1, 1) |
| C1 | HDT | | INCH | 00-000-00-0 | 3 | 4 | 68 | 1 | 1 | (0, 1, 1) |
| C2 | HDT | | INCH | 00-000-00-0 | 3 | 4 | 68 | 1 | 1 | (0, 1, 1) |
| FEP | HDT | | VOLT | 00-000-00-0 | 3 | 4 | 68 | 1 | 1 | (0, 1, 1) |
| RB | HDT | | DEG | 00-000-00-0 | 3 | 4 | 68 | 1 | 1 | (0, 1, 1) |

Then there is a couple of tables, the first summarises the X axis and the second summarises each channel (min, max mean etc.), for example:

LIS analysis of ../../../../TDTestData/LIS/pLogicTestData_med/LIS/13615.S3

Overview — Documentation Apple Yahoo! Google Maps YouTube Wikipedia News (225) Popular ▾

X Axis Information

| | Value |
|--------------------------|------------------|
| From | 17119.000 (FEET) |
| To | 16632.883 (FEET) |
| Interval | -486.117 (FEET) |
| Total number of frames | 1824 |
| Overall frame spacing | -0.267 (FEET) |
| Original recording units | b'.1IN' |

Frame Data

| Sc Name | Units | Count | Min | Mean | Max | StdDev | -- | == | ++ |
|---------|-------|-------|---------|---------|---------|----------|-------|------|-------|
| FC0 | | 29184 | 1 | 100.457 | 255 | 79.2557 | 9633 | 9633 | 9917 |
| FC1 | | 29184 | 0 | 88.7988 | 255 | 82.9932 | 10219 | 8393 | 10571 |
| FC2 | | 29184 | 0 | 93.4661 | 255 | 83.5306 | 9801 | 9250 | 10132 |
| FC3 | | 29184 | 1 | 114.45 | 255 | 76.1916 | 9543 | 9686 | 9954 |
| FC4 | | 29184 | 1 | 92.0765 | 255 | 83.5217 | 9908 | 9148 | 10127 |
| STAT | | 1824 | 0 | 0 | 0 | nan | 0 | 1823 | 0 |
| REF | | 1824 | 0 | 0 | 0 | nan | 0 | 1823 | 0 |
| REFC | | 1824 | 0 | 0 | 0 | nan | 0 | 1823 | 0 |
| EMEX | | 1824 | 0 | 0 | 0 | nan | 0 | 1823 | 0 |
| PADP | | 1824 | 0 | 0 | 0 | nan | 0 | 1823 | 0 |
| TEMP | | 1824 | 0 | 0 | 0 | nan | 0 | 1823 | 0 |
| FEP1 | | 1824 | 0 | 0 | 0 | nan | 0 | 1823 | 0 |
| FEP2 | | 1824 | 0 | 0 | 0 | nan | 0 | 1823 | 0 |
| RAC1 | | 1824 | 0 | 0 | 0 | nan | 0 | 1823 | 0 |
| RAC2 | | 1824 | 0 | 0 | 0 | nan | 0 | 1823 | 0 |
| PIAZ | DEG | 1824 | 1.69282 | 173.73 | 359.983 | 104.172 | 78 | 41 | 1704 |
| DEVI | DEG | 1824 | -0.2 | 4.11568 | 5.8 | 1.09273 | 41 | 1713 | 69 |
| HAZI | DEG | 1824 | 127.8 | 215.584 | 347.4 | 30.3939 | 256 | 1288 | 279 |
| C1 | INCH | 1824 | 4 | 6.40827 | 8.51 | 0.531151 | 173 | 1486 | 164 |
| C2 | INCH | 1824 | 4 | 6.49762 | 8.51 | 0.51583 | 180 | 1473 | 170 |
| FEP | VOLT | 1824 | 1 | 172.815 | 194 | 45.16 | 198 | 1451 | 174 |
| RB | DEG | 1824 | 0 | 187.687 | 360 | 103.195 | 63 | 69 | 1691 |

[To top](#)

tdlistablehistogram

Provides a count of elements in LIS tables.

Arguments

1. A path to a LIS file or directory of LIS files.

Options

| Option | Description |
|-------------------------------------|-----------------------------------------------------------------------------------|
| --version | Show program's version number and exit |
| -h, --help | Show this help message and exit. |
| -k, --keep-going | Keep going as far as sensible. [default: False] |
| -r, --recursive | Process input recursively. [default: False] |
| -s, --structure | Display table structure (row/col range). [default: False] |
| --type=LRTYPE | Logical record table type e.g. 34. [default: 34] |
| --name=NAME | Logical record table name e.g. PRES. [default:] |
| --row=ROW | Logical record table row e.g. "GR ". [default:] |
| --col=COL | Logical record table column e.g. "LEDG". [default:] |
| -l LOGLEVEL, --loglevel=LOGLEVEL | Log Level (debug=10, info=20, warning=30, error=40, critical=50) [default: 20] |

Examples

Count of all entries regardless of the table/row/column that they appear in:

```
$ ``tdlisttablehistogram`` -l 40 Simple/
Cmd: TableHistogram.py -l 40 Simple/
===== Count of all table entries =====
{ "(34, b'      ')": 1414,
  "(34, b'0.445')": 5,
  "(34, b'0.621')": 5,
  "(34, b'013529700231')": 7,
  "(34, b'1')": 5,
  "(34, b'1.22')": 5,
  "(34, b'1.70')": 2,
  "(34, b'116')": 2,
  "(34, b'12.25')": 2,
  "(34, b'15')": 5,
  "(34, b'15-4-76')": 5,
  "(34, b'17')": 5,
  "(34, b'17.5')": 5,
  "(34, b'19')": 5,
  "(34, b'1976')": 7,
  "(34, b'2')": 2,
  "(34, b'2055.0')": 2,
  "(34, b'2071.2')": 4,
  "(34, b'25')": 2,
  "(34, b'25-6-76')": 2,
  "(34, b'257.0')": 7,
  ...
  "(34, b'WN  ')": 7,
  "(34, b'YEAR')": 7,
  '(34,)': 443}
===== Count of all table entries END =====
CPU time =    0.205 (S)
Bye, bye!
```

The result is a dictionary that has the key as a pair (lr_type, cell_value) and the value as a count of the number of occurrences.

If the -s option is used then an additional summary is provided:

```
===== Row entries =====
{(34, b'CONS', b'APIN'): 7,
 (34, b'CONS', b'BLI '): 7,
 (34, b'CONS', b'BS1 '): 7,
 (34, b'CONS', b'BS2 '): 7,
 (34, b'CONS', b'BS3 '): 7,
 ...
 (34, b'CONS', b'WN '): 7,
 (34, b'CONS', b'YEAR'): 7}
===== Row entries END =====
===== Column entries =====
{(34, b'CONS', b'ALLO'): 707,
 (34, b'CONS', b'MNEM'): 707,
 (34, b'CONS', b'PUNI'): 707,
 (34, b'CONS', b'TUNI'): 707,
 (34, b'CONS', b'VALU'): 707}
===== Column entries END =====
```

This are dictionaries that have the key as a tripple (lr_type, table_name, row_name) and (lr_type, table_name, column_name) respectively and the value as a count of the number of occurrences.

Filtering by Logical Record type, table name, row name and column name (note quoting of spaces):

```
$ ``tdlistablehistogram`` -l 40 --type=34 --name=CONS --row="WN " --col=VALU Simple/
Cmd: TableHistogram.py -l 40 --type=34 --name=CONS --row=WN --col=VALU Simple/
===== Count of all table entries =====
{"(34, b'CONS', b'WN ', b'VALU', b'B897 - 14')": 1,
 "(34, b'CONS', b'WN ', b'VALU', b'DIEKSAND 111A')": 3,
 "(34, b'CONS', b'WN ', b'VALU', b'VOELKERSEN AZ4')": 3}
===== Count of all table entries END =====
CPU time = 0.174 (S)
Bye, bye!
```

The result is a dictionary that has the key as a quadruple (lr_type, table_name, row_name, column_name, cell_value) and the value as a count of the number of occurrences.

LIS Developer Tools

tdlisdetif

Takes an input LIS79 file and writes out a new one without TIF markers.

Arguments

1. The path to the input LIS file.
2. The path to the output LIS file, any directories will be created as necessary.

Options

| Option | Description |
|-------------------------------------|--------------------------------------------------------------------------------|
| --version | Show program's version number and exit |
| -h, --help | Show this help message and exit. |
| -n, --nervous | Nervous mode (do no harm). [default: False] |
| -l LOGLEVEL, --loglevel=LOGLEVEL | Log Level (debug=10, info=20, warning=30, error=40, critical=50) [default: 20] |

Examples

DeTIF with nervous mode just examines the file:

```
$ ``tdlisdetif`` -n RW.lis RW_No_TIF.lis
Cmd: DeTif.py -n RW.lis RW_No_TIF.lis
stripTif(): Tell: 0x00000000 Len: 0x00000000 TIF: TIF True >: 0x      0 0x      ]
↪0 0x      0
stripTif(): Tell: 0x0000000c Len: 0x0000003e TIF: TIF True >: 0x      0 0x      ]
↪0 0x      4a
stripTif(): Tell: 0x00000056 Len: 0x00000400 TIF: TIF True >: 0x      0 0x      ]
↪0 0x      456
stripTif(): Tell: 0x00000462 Len: 0x00000400 TIF: TIF True >: 0x      0 0x      ]
↪4a 0x      862
stripTif(): Tell: 0x0000086e Len: 0x00000400 TIF: TIF True >: 0x      0 0x      ]
↪456 0x      c6e
stripTif(): Tell: 0x00000c7a Len: 0x00000400 TIF: TIF True >: 0x      0 0x      ]
↪862 0x      107a
stripTif(): Tell: 0x00001086 Len: 0x00000400 TIF: TIF True >: 0x      0 0x      ]
↪c6e 0x      1486
stripTif(): Tell: 0x00001492 Len: 0x00000400 TIF: TIF True >: 0x      0 0x      ]
↪107a 0x      1892
stripTif(): Tell: 0x0000189e Len: 0x00000400 TIF: TIF True >: 0x      0 0x      ]
↪1486 0x      1c9e
...
stripTif(): Tell: 0x000d2b4e Len: 0x000000f6 TIF: TIF True >: 0x      0 0x      ]
↪d2748 0x      d2c44
stripTif(): Tell: 0x000d2c50 Len: 0x0000003e TIF: TIF True >: 0x      0 0x      ]
↪d2b42 0x      d2c8e
CPU time = 0.022 (S)
Exec. time = 0.022 (S)
Bye, bye!
```

DeTIF with write:

```
$ ``tdlisdetif`` RW.lis RW_No_TIF.lis
Cmd: DeTif.py RW.lis RW_No_TIF.lis
CPU time = 0.019 (S)
Exec. time = 0.019 (S)
Bye, bye!
```

tdlisindex

This indexes a LIS file and prints out the result. It can also provide some performance measurements of the indexing operation. See *Indexing LIS Files* for more information about the design and performance of LIS indexing.

Arguments

1. The path to a LIS file or a directory of LIS files.

Options

| Option | Description |
|-------------------------------------|---------------------------------------------------------------------------------------------------------------------|
| --version | Show program's version number and exit |
| -h, --help | Show this help message and exit. |
| -k, --keep-going | Keep going as far as sensible. [default: False] |
| -l LOGLEVEL, --loglevel=LOGLEVEL | Log Level (debug=10, info=20, warning=30, error=40, critical=50) [default: 20] |
| -j JOBS, --jobs=JOBS | Max processes when multiprocessing. Zero uses number of native CPUs [8]. -1 disables multiprocessing. [default: -1] |
| -t TIMES, --times=TIMES | Number of times to repeat the read [default: 1] |
| -s, --statistics | Dump timing statistics. [default: False] |
| -v, --verbose | Verbose output, this outputs a representation of table data and DFSRs. |
| -r, --recursive | Process input recursively. [default: False] |

Examples

Simple scan of a single file:

```
$ ``tdlisindex`` Simple/LIS.lis
Cmd: Index.py Simple/LIS.lis
2012-02-09 09:36:28,039 INFO      Index.indexFile(): Simple/LIS.lis
File size: 17708 (0.017 MB) Reference Time: 0.002459 (s) for Simple/LIS.lis
↳pickleLen=4351 jsonLen=-1
Summary:
Results:      1
Errors:       0
Total:        1
CPU time =    0.004 (S)
Bye, bye!
```

Simple scan of a single file with verbose output:

```
$ ``tdlisindex`` -v Simple/LIS.lis
Cmd: Index.py -v Simple/LIS.lis
2012-02-09 09:39:29,493 INFO      Index.indexFile(): Simple/LIS.lis
<TotalDepth.LIS.core.FileIndexer.FileIndex object at 0x10197fdd0> "Simple/LIS.lis"
↳[4]:
  tell: 0x00000000 type=128 <TotalDepth.LIS.core.FileIndexer.IndexFileHead object at
↳0x10197fe10>
  tell: 0x0000003e type= 34 name=b'CONS' <TotalDepth.LIS.core.FileIndexer.IndexTable
↳object at 0x10197fe90>
```

```

<TotalDepth.LIS.core.LogPass.LogPass object at 0x101b071d0>
tell: 0x000044ee type=129 <TotalDepth.LIS.core.FileIndexer.IndexFileTail object at
↳0x101b077790>
===== All records =====
tell: 0x00000000 type=128 <TotalDepth.LIS.core.FileIndexer.IndexFileHead object at
↳0x10197fe10>
tell: 0x0000003e type= 34 name=b'CONS' <TotalDepth.LIS.core.FileIndexer.IndexTable
↳object at 0x10197fe90>
<TotalDepth.LIS.core.LogPass.LogPass object at 0x101b071d0>
tell: 0x000044ee type=129 <TotalDepth.LIS.core.FileIndexer.IndexFileTail object at
↳0x101b077790>
===== All records DONE =====
===== Log Passes =====
LogPass <TotalDepth.LIS.core.LogPass.LogPass object at 0x101b071d0>:
  DFSR: <TotalDepth.LIS.core.LogiRec.LrDFSRRRead object at 0x10197ff90>: "Data
↳format specification record"
  Frame plan: <TotalDepth.LIS.core.Type01Plan.FrameSetPlan object at 0x101b07210>:
↳indr=0 frame length=24 channels=6
    Channels: [b'DEPT', b'SP ', b'SN ', b'ILD ', b'CILD', b'DT ']
    RLE: <TotalDepth.LIS.core.Rle.RLEType01 object at 0x101b07250>: func=None:
↳[RLEItemType01: datum=8592 stride=1014 repeat=7 frames=42, RLEItemType01:
↳datum=16704 stride=None repeat=0 frames=39]
    X axis: first=2052.983 last=1995.986 frames=375 overall spacing=-0.1524 in
↳optical units=b'M ' (actual units=b'M ')
    Frame set: None

===== Log Passes DONE =====
===== Plot Records =====
===== Plot Records DONE =====

  Min: 0.003 (s)
  Max: 0.003 (s)
  Mean: 0.003 (s)
File size: 17708 (0.017 MB) Reference Time: 0.002529 (s) for Simple/LIS.lis
↳pickleLen=4351 jsonLen=-1
Summary:
Results:      1
Errors:       0
Total:        1
CPU time =    0.004 (S)
Bye, bye!

```

Scan of a directory (recursively) indexing each file 11 times and writing out statistics:

```

$ ``tdlisindex`` -t11 -s -l 40 Simple/
Cmd: Index.py -t11 -s -l 40 ../../../../TDTestData/LIS/Simple
File size: 17708 (0.017 MB) Reference Time: 0.001670 (s) for Simple/LIS.lis
↳pickleLen=4351 jsonLen=-1
File size: 863374 (0.823 MB) Reference Time: 0.043411 (s) for Simple/RW.lis
↳pickleLen=18231 jsonLen=-1
File size: 853030 (0.814 MB) Reference Time: 0.039238 (s) for Simple/RW_No_TIF.lis
↳pickleLen=18238 jsonLen=-1
Summary:
Size (kb)    Time (s)
17.293       0.001670
843.139      0.043411
833.037      0.039238

Files: 3

```

```
Errors: 0
CPU time = 0.938 (S)
Bye, bye!
```

tdXlisrandomframesetread

For developers only. This is designed to measure the performance of loading and iterating across a frame-set.

1.6 Usage In a Python Project

To use TotalDepth:

```
import TotalDepth
```

1.6.1 Important Concepts

Due to the size of data TotalDepth makes extensive use of lazy evaluation and generators, this means that compute power is only used where necessary.

Log Pass

A *Log Pass* represents a typical, independent, logging recording consisting of a format specification plus binary data. The format specification defines how to interpret the binary data (number of channels, name and units for each channel). In the LIS format the formatting record is known as the *Data Format Specification Record (DFSR)*. A “Repeat Section” plus a “Main Log” are two, distinct, independent Log Passes.

Frame Set

A *Frame Set* is the logging data converted to the platforms internal types (usually C doubles) and stored in memory as a table where each row represents a particular depth (or time) and each column is the output of a specific channel. Each row is often referred to as a *Frame*

1.7 Processing LIS Files

1.7.1 Important LIS Concepts

LIS File

A LIS file is a wrapper round the platforms native I/O system.

Reference: `TotalDepth.LIS.core.File.FileRead`

LIS Index

The LIS file format is designed for recording rather than processing. As such it is a sequential self announcing format where to understand any part of it you have to have processed all of the preceeding data. This becomes very expensive with large files.

To avoid this an index is first created for the file that then allows random access to any part of that file including an individual frame. All access to the file is using this index. This index is very fast to create and its size is typically 1% of the original file size.

Reference: `TotalDepth.LIS.core.FileIndexer.FileIndex`

1.7.2 Reading a LIS File Table Data

Suppose that we have a file in `~/tmp/LIS.lis` and you want to read the well site data. First import what we need:

```
>>> import TotalDepth
>>> from TotalDepth.LIS.core import File
>>> from TotalDepth.LIS.core import FileIndexer
>>> import os
```

Then open the LIS file and create an index from it:

```
>>> fpath = os.path.expanduser('~tmp/LIS.lis')
>>> lis_file = TotalDepth.LIS.core.File.FileRead(fpath)
>>> lis_index = TotalDepth.LIS.core.FileIndexer.FileIndex(lis_file)
```

There is a method on the index `genAll()` that iterates through all the records, filter this for only table data:

```
>>> from TotalDepth.LIS.core import LogiRec
>>> cons_records = [lr for lr in lis_index.genAll() if lr.lrType in LogiRec.LR_TYPE_
↳TABLE_DATA]
>>> cons_records
[<TotalDepth.LIS.core.FileIndexer.IndexTable object at 0x103ac3dd8>]
```

In this file there is only one table record. Now read it:

```
>>> lis_file.seekLr(cons_records[0].tell)
>>> table = LogiRec.LrTableRead(lis_file)
```

Now we can explore the table:

```
>>> table.desc
'Well site data'
>>> table.value
b'CONS'
>>> table.colLabels()
odict_keys([b'MNEM', b'ALLO', b'PUNI', b'TUNI', b'VALU'])
>>> table.rowLabels()
dict_keys([b'HIDE', b'HID1', b'HID2', b'CN ', b'WN ', ..., b'C30 '])
```

Notice all the entries are represented as Python bytes objects (`b' ... '`), this is because LIS does not support Unicode. LIS is also a bit shouty.

To get a specific value, say the well name:

```
>>> print(table[b'WN  '][b'VALU'])
CB: type=69 rc=65 size=16 mnem=b'VALU' EngValRc: b'GUSHER'
>>> table[b'WN  '][b'VALU'].value
b'GUSHER'
```

You can index by integer:

```
>>> table[4][0].value
b'WN  '
>>> table[4][4].value
b'GUSHER'
>>> [v.value for v in table[4]]
[b'WN  ', b'ALLO', b'      ', b'      ', b'GROSSENKNETEN Z2']
```

You can index by slice:

```
>>> [v.value for v in table[4][:2]]
[b'WN  ', b'ALLO']
```

To print the whole table there are some generators for this:

```
>>> for row in table.genRows():
...     for col in row.genCells():
...         print(col.value, ' ', end='')
...     print()
...
b'HIDE' b'ALLO' b'      ' b'      ' b'      ' b'MAIN LOG'
b'HID1' b'ALLO' b'      ' b'      ' b'      ' b'RAW DATA'
b'HID2' b'ALLO' b'      ' b'      ' b'      ' b'
b'CN   ' b'ALLO' b'      ' b'      ' b'      ' b'BIG COMPANY'
b'WN   ' b'ALLO' b'      ' b'      ' b'      ' b'GUSHER'
...
```

Reference: *TotalDepth.LIS.core.LogiRec.LrTable*

1.7.3 Reading a LIS File Log Data

Suppose that we have a file in `~/tmp/LIS.lis` and you want to read the frame data from a particular log pass, first import what we need:

```
>>> import TotalDepth
>>> from TotalDepth.LIS.core import File
>>> from TotalDepth.LIS.core import FileIndexer
>>> import os
```

Then open the LIS file and create an index from it:

```
>>> fpath = os.path.expanduser('~'/tmp/LIS.lis')
>>> lis_file = TotalDepth.LIS.core.File.FileRead(fpath)
>>> lis_index = TotalDepth.LIS.core.FileIndexer.FileIndex(lis_file)
```

There is a method on the index `genLogPasses()` that iterates through the log passes, lets get them all:

```
>>> log_passes = list(lis_index.genLogPasses())
>>> print(log_passes)
[<TotalDepth.LIS.core.FileIndexer.IndexLogPass object at 0x103ac3e80>]
```

In this file there is only one log pass, we can get the description of it using `longstr()`:

```
>>> print(log_passes[0].logPass.longStr())
<TotalDepth.LIS.core.LogPass.LogPass object at 0x103ae10b8>:
  DFSR: <TotalDepth.LIS.core.LogiRec.LrDFSRead object at 0x103ac3eb8>: "Data_
↳format specification record"
  Frame plan: <TotalDepth.LIS.core.Type01Plan.FrameSetPlan object at 0x103ae10f0>:
↳indr=0 frame length=24 channels=6
    Channels: [b'DEPT', b'SP ', b'SN ', b'ILD ', b'CILD', b'DT ']
    RLE: <TotalDepth.LIS.core.Rle.RLEType01 object at 0x103ae1128>: func=None:
↳[RLEItemType01: datum=8592 stride=1014 repeat=7 frames=42, RLEItemType01:
↳datum=16704 stride=None repeat=0 frames=39]
    X axis: first=2052.983 last=1995.986 frames=375 overall spacing=-0.1524 in
↳optical units=b'M ' (actual units=b'M ')
  Frame set: None
```

Note the last line `Frame set: None`, this is because the log pass is a lightweight object which does not (yet) contain all the frame data. To read all the frame data from the file we call `setFrameData(LisFile)` on the log pass:

```
>>> log_passes[0].logPass.setFrameSet(lis_file)
```

Now the frame set is fully populated:

```
>>> print(list(log_passes[0].logPass.genFrameSetScNameUnit()))
[('DEPT', 'M '), ('SP ', 'MV '), ('SN ', 'OHMM'), ('ILD ', 'OHMM'), ('CILD',
↳'MMHO'), ('DT ', 'US/M')]
```

To get the actual vales in the frame we can access the numpy array directly:

```
>>> data = log_passes[0].logPass.frameSet.frames
>>> data
array([[ 2.05298340e+03, -4.54907703e+00,  1.34538269e+00,
         1.26347518e+00,  3.86598633e+02, -9.99250000e+02],
       [ 2.05283105e+03, -5.13720322e+00,  1.36061692e+00,
         1.29521227e+00,  5.00510803e+02, -9.99250000e+02],
       [ 2.05267871e+03, -6.66747475e+00,  1.38543439e+00,
         1.45785594e+00,  5.95623291e+02, -9.99250000e+02],
       ...,
       [ 1.99629077e+03, -9.99250000e+02, -9.99250000e+02,
        -9.99250000e+02, -9.99250000e+02, -9.99250000e+02],
       [ 1.99613843e+03, -9.99250000e+02, -9.99250000e+02,
        -9.99250000e+02, -9.99250000e+02, -9.99250000e+02],
       [ 1.99598608e+03, -9.99250000e+02, -9.99250000e+02,
        -9.99250000e+02, -9.99250000e+02, -9.99250000e+02]])
```

Now, if you are familiar with numpy then all normal operations are possible, for example get the X axis:

```
>>> data[:,0]
array([ 2052.98339844,  2052.83105469,  2052.67871094,  2052.52636719,
        2052.37402344,  2052.22167969,  2052.06933594,  2051.91650391,
        2051.76416016,  2051.61181641,  2051.45947266,  2051.30712891,
        ...,
        1996.29077148,  1996.13842773,  1995.98608398])
```

Find the min, mean, max:

```
>>> data.min(axis=0)
array([ 1995.98608398, -999.25      , -999.25      , -999.25      ,
       -999.25      , -999.25      ])
>>> data.mean(axis=0)
array([ 2024.48480339, -305.07223682, -326.84234802, -324.20620109,
        206.05499658,  28.2555695  ])
>>> data.max(axis=0)
array([ 2.05298340e+03, -7.69491196e-01,  1.98412299e+00,
        2.34852839e+00,  1.75242944e+03,  4.59522583e+02])
```

References:

LogPass: `TotalDepth.LIS.core.LogPass.LogPass`

FrameSet: `TotalDepth.LIS.core.FrameSet.FrameSet`

1.8 Processing LAS Files

TODO:

1.9 TotalDepth Technical Notes

This collect together various technical descriptions of how TotalDepth solves certain problems.

Contents:

1.9.1 Indexing LIS Files

Most petrophysical files are recorded in real time and the recording format is sequential, thus everything depends on what has gone before. This is not very satisfactory for the user who might well wish to access the data in a arbitrary manner - “give me these curves over this interval”. The solution is to create an index to the original file so that it can be accessed *as if* it is a random access file.

Here we describe how that indexing works and the performance it achieves for the user.

Introduction

The LIS file format is a binary, self describing, sequential format with multiple layers of encoding and, in practice, no forward references. LIS files can be large and, generally speaking, the greater part of the file consists of frame data whose format is invariant within any particular *Log Pass*.

In a dynamic situation, such as a user reading the file, the *instantaneous* amount of data needed from a LIS file is small compared with the file size. For example plotting 200 feet of a 50Mb file might need only 1/3000 of the data in the file. As the LIS file format is geared to sequential recording, not random access, accessing such a small amount efficiently needs additional software cunning.

TotalDepth’s approach to this is to use *indexing*. The essential requirements for an indexer are:

- Fast to create an index.
- The index is small.
- The index has sufficiently useful granularity.

- The index can be serialised in a number of ways (as a minimum; XML, binary (e.g. ‘pickle’), JSON?).
- The indexer design is flexible and extensible.

Apart from the cost of design and coding a solution the cost/benefit of indexing can be measured thus:

- The time to creating an index.
- The space required by the index, in-memory or serialised in some form.
- The time, in $O(N)$, terms of accessing N bytes of data.

A design that has low time/space requirements is regarded as a ‘good’ design.

Indexing Design

TotalDepth’s LIS indexer works on several levels:

| Level | Description |
|-----------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| File Level | Indexing of the position of all Logical Records |
| Logical Records with frame data | Runs of these can be efficiently indexed with Run Length Encoding |
| Within a Logical Record containing frame data | Accessing a particular frame and channel can be by computation with the help of a frame index. In particular this can identify seek/read sequences of any value from any channel in $O(1)$ time. |

Indexing a LIS File

The intention is to find the start position of each Logical Record and a minimal amount of information of that Logical Record. The start position is the `size_t` value of the file index of, either, the start of the TIF marker for the first Physical Record in the Logical Record (if TIF encoded), or, the start of the first Physical Record in the Logical Record (if *not* TIF encoded).

As well as recording the file position of the Logical Record the indexer retrieves part or all of the Logical Record contents. This is specialised by Logical Record type thus:

| Logical Record | Index Contents |
|---------------------------------|------------------------------------------------------------------------------------------------------------------|
| Reel/Tape/File Header/Trailer | The complete contents of the Logical Record. These are small (58 or 128 bytes) but possibly important. |
| Table records | The Logical Record header and the first Component Block. These are variable, large, but possibly important. |
| DFSR | The complete contents of the Logical Record. These are variable size, not particularly large and very important. |
| Logical Records with frame data | Indexed as part of a Log Pass with a RLE object. This records the Logical Record header and the first data word. |
| All other Logical Records | The Logical Record header only. |

Module

The Python module that performs file indexing is `TotalDepth.LIS.core.FileIndexer`

For reference documentation see: [FileIndexer](#).

Example

The LIS package has an Index.py module that will index any LIS file. Here is some (selected) output of a single file:

```
===== All records =====
tell: 0x00000000 type=128 <TotalDepth.LIS.core.FileIndexer.IndexFileHead object at_
↳0x101b09050>
tell: 0x0000004a type= 34 name=b'CONS' <TotalDepth.LIS.core.FileIndexer.IndexTable_
↳object at 0x101b090d0>
<TotalDepth.LIS.core.LogPass.LogPass object at 0x101b09450>
tell: 0x0006141c type=129 <TotalDepth.LIS.core.FileIndexer.IndexFileTail object at_
↳0x101b0c110>
tell: 0x00061466 type=128 <TotalDepth.LIS.core.FileIndexer.IndexFileHead object at_
↳0x101b0c190>
tell: 0x000614b0 type= 34 name=b'CONS' <TotalDepth.LIS.core.FileIndexer.IndexTable_
↳object at 0x101b0c210>
<TotalDepth.LIS.core.LogPass.LogPass object at 0x101b0c510>
tell: 0x00065a44 type=129 <TotalDepth.LIS.core.FileIndexer.IndexFileTail object at_
↳0x101b0cad0>
tell: 0x00065a8e type=128 <TotalDepth.LIS.core.FileIndexer.IndexFileHead object at_
↳0x101b0cb50>
tell: 0x00065ad8 type= 34 name=b'CONS' <TotalDepth.LIS.core.FileIndexer.IndexTable_
↳object at 0x101b0cbd0>
<TotalDepth.LIS.core.LogPass.LogPass object at 0x101b0cfd0>
tell: 0x000d2c44 type=129 <TotalDepth.LIS.core.FileIndexer.IndexFileTail object at_
↳0x101b10450>
===== All records DONE =====
```

Note that the indexing of a Log Pass is separate since it covers an EFLR and zero or more IFLRs. This is the subject of the next section.

Indexing a Log Pass

A Log Pass is described by an EFLR and zero or more IFLRs. In LIS terms this means a DFSR and the associated binary IFLRs. This is a candidate for fairly aggressive optimisation since:

- In practice the Logical Records containing the IFLRs are normally adjacent and regular (same size).
- The frame structure is invariant.

Supposing a Log Pass has 18 data channels using representation code 68 (frame length 72 bytes) and each IFLR record contains 24 frames (24*72=1728 bytes). If there are 72 Logical Records then it is fairly easy to calculate where, in logical space, logical record x is in the file; start + $x * 1728$ ¹.

NOTE: The following describes some of the internals of Log Pass indexing, it is for information only as the LogPass and IndexLogPass objects do this automatically.

Run Length Encoding of Logical Records

Run Length Encoding (RLE) is an encoding system that is highly efficient at describing regularly spaced intervals. Since LIS is primarily a recording format the recording software will create and suitably sized buffer for an integer number of frames and other environmental parameters. During recording the buffer will be filled frame by frame. When the buffer is full the buffer will be flushed to file. So a continuous series of IFLRs tends to consist of a series of

¹ Illustrative only, it is slightly more complicated than this.

adjacent Logical Records of the same size followed, possibly, by a single terminating Logical Record that is shorter (by an integer number of frames) than the others.

Module

The Python module that performs RLE of Logical Records is `TotalDepth.LIS.core.Rle`

For reference documentation see: [Run Length Encoding Module](#).

Indexing Frame Data

This describes how an index is created to find arbitrary values in a Logical Record containing Frame Data.

Supposing a Log Pass has 18 data channels using representation code 68 (frame length 72 bytes) and each IFLR record contains 24 frames. If there are 72 Logical Records then it is a simple² task to calculate where, in logical space, the bytes for channel x and frame y are.

Module

The Python module that performs indexing within a Logical Record containing frame data is `TotalDepth.LIS.core.Type01Plan`.

For reference documentation see: [Type01Plan](#).

Indexing Performance

As mentioned above the cost of indexing can be measured with these independent measures:

- The time to creating an index.
- The space required by the index, in-memory or serialised in some form.
- The time per byte to access N bytes of data.
- Any deviation from O(N) performance, N being total file size or size of data read.

The following data was measured using 300+ LIS files totalling of around 300+Mb, the largest being around 50Mb. The LIS module `TotalDepth.LIS.RandomFrameSetRead.py` was used to conduct the tests.


The original targets for the cost of TotalDepth LIS indexing were:

| Cost ms/Mb | Result |
|------------|----------------|
| <15 | Excellent |
| 15-50 | Good |
| 50-100 | Satisfactory |
| >100 | Unsatisfactory |

² Well not that simple, there is indirect X-axis to take into account and several other things.

Index Time

This is simply the actual time taken to create a file level index:



The best fit of all points is the cyan line (index(x) on the plot legend). The best fit for the lines is:


| Line | Description | Colour | Latency (ms) | Cost (ms/Mb) | Result |
|-------------|------------------------------|---------|--------------|--------------|--------------|
| PR_1kB(x) | Physical Record length = 1kb | Green | 1.3 | 80 | Satisfactory |
| PR_8kB(x) | Physical Record length = 8kb | Blue | 1.2 | 12 | Excellent |
| PR_DontKnow | Upper bound, worst case | Magenta | 3.0 | 90 | Satisfactory |
| index(x) | Regression fit on all points | Cyan | 1.2 | 39.9 | Good |

However there are some other trends that can be teased out when separating files that have Physical Records of 1kb and those in the data set that have 8kb Physical Records (there were no larger Physical Record sizes in the data set). The green fit (PR_1kB(x) on the plot legend) is the best fit for those files that have Physical Records of 1kb. The blue line (PR_8kB(x) on the plot legend) is the best fit for files that have Physical Records of 8kb, it is almost exactly 8 times faster.

In fact in other tests, not presented here, it was shown that there was a linear speedup with Physical Record size up to their maximum size of 64kb. In fact the dominant factor in indexing time was the *number of physical records*. This suggests a couple of things:

- Before archiving or processing LIS files rewrite them to their maximum Physical Record size (64kb). This will pay off later when indexing prior to any read operation.
- Rewrite the Physical Record handler (and below) in C or Cython as it seems to be the bottleneck for indexing.

This is actual time taken to create a file level index divided by the file size. This gives some measure of ‘cost’ which is defined here as ms per Mb of data processed, here the size in Mb is the total file size:




The rising costs for smaller files is no real cause for concern, this represents the startup cost of indexing and reading of around 1 to 2 ms. This graph clearly demonstrates $O(N)$, or better, behaviour.

Again the advantage in having 8kb Physical Records is evident in the lower right hand corner. The cost would be further reduced to around 1 to 1.5 ms/Mb by having 64kb Physical Records.

Multi-Processing

Most of TotalDepth software supports parallel processing. The LIS command line tool Index.py can create indexes in parallel. The following graph shows the file size plotted against total time to index when indexing around 300 LIS files with different numbers of simultaneous processes. The red line is the best fit for single process indexing that costs about 40 ms/Mb:



The index time rises slightly with increasing number of processes and the scatter rises dramatically with 8 processes presumably because of I/O contention.

Actual wall clock times for indexing all those LIS files for different numbers of simultaneous processes on a four core machine with hyper-threading are:

| Processes | Total time to index (s) | Improvement over No multiprocessing |
|--------------------|-------------------------|-------------------------------------|
| No multiprocessing | 18.4 | Datum |
| 1 | 18.3 | 0.995 |
| 2 | 9.9 | 0.538 |
| 4 | 8.9 | 0.484 |
| 8 | 7.6 | 0.413 |

Moving to two processes gives an almost linear speedup, moving from two to four or eight processes gives only slight improvement presumably because the execution time becomes I/O bound.

Index Size

It is envisaged that the index will be persisted in some form. Once persisted then the LIS file would only be accessed via the index, any file write operation requires a suitable adjustment to the index.

Persistence techniques could be, for example:

- Stored in a database.
- Serialised in binary form onto the file system.


- Serialised in human readable form, such as XML, onto the file system or database³.
- Serialised in binary form and attached as a Logical Record to the LIS file it refers to.

TotalDepth and SaaS

There is a further imperative to understanding index size; if TotalDepth were to be used, as it was always intended, as Software as a Service (SaaS) where the bulk of the processing is with the data file on the client machine and the processing done on the server then part of the bootstrap process of any transaction is for the client to index the file and send the index to the server. In that case it is important to keep the index size small.

Thus the size of the index content is a significant consideration.

The following graph measures the size of the index when serialised with Python's `cPickle` module, Pickled size is in kb (red markers, left scale) and compared as a percentage of the original file size (green markers, right scale):



The pickled size shows a wide range that is representative of the wide range of LIS inputs. The best fit for size (albeit with a large scatter) is 5kb + 0.6% of the file size which is entirely satisfactory [the upper bound being 42kb + 2.3% and the lower bound being just 1.2kb + 0.08% with larger files tending towards the lower bound].

The relative size of the index shows a strong downward trend (blue line) for files below 4Mb, before levelling off at the 0.1 to 3% mark. This is quite satisfactory for the use cases described above including SaaS. This graph clearly demonstrates $O(N)$, or better, behaviour.

³ JSON can not handle the index in its current form.

Indexing Performance Improvements

As noted above there is a substantial improvement in indexing when large Physical Record sizes are used.

It is also likely that significant improvement could be made if the RawStream, TifMarker and PhysRec were to be rewritten in C/C++ or Cython. The PhysRec module has a dependency on the RepCode module (easily removed). All three modules have a dependency on the struct module so the limited functionality that they use from there would have to be reproduced, thats pretty easy since it only involves integer manipulation.

So given an ‘average’ cost of indexing of 40 ms/Mb (i.e. a ‘good’ rating) the performance improvements could be:

- Moving to larger Physical Record sizes: x8?
- Integrate the existing (in another project) code in C that handles Raw Stream/TIF/Physical Record handling into this project. This is known to be about x100 faster (and the index has a lower memory footprint).

The performance improvements would not necessarily combine as they are mutually dependent but the combination might reduce the cost to around 2 to 8 ms/MB, an exceptionally good performance indeed.

See *Performance Improvements* for other performance improvements

LIS Read Performance via an Index

This is described here *Performance of TotalDepth*

Summary

Indexing is not free, it incurs an overhead, but this overhead is acceptable. The overhead is worst for small data sizes where the performance is high in any case. The overhead is low, and the benefit is very great for large or complex data sizes where the performance, without indexing, could be very poor indeed.

1.9.2 Performance of TotalDepth

This technical note presents the results of some actual performance tests on TotalDepth.

Measuring Performance

This describes some principles used in establishing TotalDepth’s performance and setting performance targets.

User’s Perception of Performance

Users only want to pay for what they get and experienced users have a rough idea of the cost of what they ask the software to do. For example most users would regard these a cheap operations, and would not expect them to take much time. If they did the user is likely to regard the application as ‘slow’:

- Load file
- Show log header
- Plot small section

Most users would regard these more expensive operations and is more likely to accept that they would take more time.:

- Cross correlate multiple curves

- Dipmeter processing
- Deconvolution

Most users are aware of the size of the data set with which they are operating and appreciate that operations on larger data sets take longer time. Users do not appreciate $O(N^2)$ or worse behaviour. We don't like it either¹.

TotalDepth measures the cost of operations, in:

```
Execution time (ms)
-----
Size of input (Mb)
```

Example of LIS cost

Our measure is ms/Mb of input. 1Mb of LIS data is typically 250,000 values, or, to put this in context 200 feet of 10 curves (6" sampling) is 0.015 Mb. So, just as an example, the cost of plotting such data from a 20Mb file *might* work out as:

| Operation | Cost (ms/Mb) | Data Size (Mb) | User's Time (ms) | Notes |
|-----------------------------|--------------|----------------|------------------|------------------|
| Index a 20Mb file | 12 | 20 | 240 | One-off exercise |
| Reading 200 feet, 10 curves | 1500 | 0.015 | 22 | |
| Plotting what has been read | 4000 | 0.015 | 60 | |
| Total | . | . | 322 | |

The rest of this tech note describes the performance of reading LIS files in these ms/Mb terms.

Actual LIS Performance

Actual performance results of some LIS file operations.

File Read Cost


The measure here is low level reading and conversion from binary words to internal number formats. Three operations are being measured:

- Raw read speed of bytes.
- Above, and converting to internal integers and floats.
- Above and converting from Rep Code 68 to an internal float.

The input data was about 100 binary files with random data of around 100 Mb in total.

The x-axis of the graph below is the buffer length, in other words how much data is swallowed in a single atomic read.

¹ It is very easy for software developers to fail to see this kind of behaviour. For example if the time for an operation is: $a + b * N + c * N^2$ and $c \ll b$. If the software test suit tests an insufficiently small size of N then it appears that the operation is $O(N)$. Along comes a user with a large data set and they see $O(N^2)$ behaviour. This (or worse) is quite commonly observed in many software products.



Raw File Read

The ‘Read all’ graph shows the cost of reading bytes at different buffer sizes from a file and discarding it. This is the baseline and represents the crude storage access time. Large buffer sizes achieve <1 ms/Mb (1 Gb/s).

Raw File seek()

The ‘Seek all’ graph shows the cost of traversing a file using seek() at different seek lengths. No data is read. Combined with the read information this can be used to estimate the minimum time to make a series of read/seek operations.

Using the struct module

The “Read int (compiled)” and “Read float (compiled)” data shows the cost of reading bytes into a buffer and then converting them to a list of integers and floats using the struct module (the type declaration is compiled). They show an asymptotic cost, in addition to the read cost, of 8 and 3 ms/Mb respectively. This shows very good performance for reading builtin types with the struct module. As most RP66 types are builtins (or types supported by the struct module) then the struct module should be used for RP66.

It is slightly surprising that reading an integer is slower than reading a floating point number.

Reading Rep Code 68

This establishes the cost of converting a bytes object in Representation Code 68 to a internal floating point value.

The cost of using Python code and Cython code is examined and in each case the the total cost or read+convert is presented and then the integer `struct` read cost (above) is subtracted to get the conversion cost.

Python

The data sets “Read Rep Code 68 (Python)” and “Convert to Rep Code 68 (Python)” plots to the cost of reading bytes and converting them to Representation code 68, the latter curve has the read cost subtracted (from above) so it represents merely the conversion cost of in-memory from bytes to Rep Code 68. This is asymptotic to around 270 ms/Mb.

Cython

The data sets “Read Rep Code 68 (Cython)” and “Convert to Rep Code 68 (Cython)” is as immediately above but using Cython code rather than Python code. This is asymptotic to around 72 ms/Mb. This is significantly longer than using the `struct` module to interpret a IEEE float so it could be that some improvement could be made with a pure C implementation.

Cython vs Python

The “Cython/Python cost (right axis)” plots the ratio of converting Rep Code 68 with Python and Cython. The Cython code takes 0.27 of the cost of the Python code. Well worth it.

Frame Read Cost

The operation being timed here is, given a LIS file index, read a certain set of frame data then convert each value to an internal floating point number and then populate the internal `FrameSet` object. This is a basic operation before doing any plotting, channel editing, recalibration etc. The amount of data read is the cumulative size in LIS bytes of all the values read from the file. 250,000 values would constitute typically 1Mb of LIS data.

A number of different methods were use to read the LIS data:

- Method A: All frames all channels. Here indexing provides no optimisation as it is a simple sequential read operation of everything.
- Method C: A sequential subset of the frames and a sequential subset of the channels. This requires a logical seek operation to the start of the frames then, within each frame a seek then read then seek operation.
- Method D: A sequential subset of the frames and a non-sequential subset of the channels. This requires a logical seek operation to the start of the frames then, within each frame multiple seek/read operations.
- Method E: A non-sequential subset of the frames and a non-sequential subset of the channels. This requires a set of logical seek/read operations to each frame then, within each frame multiple seek/read operations.


Indexing can provide an optimisation for methods C-E as it hugely reduces the amount of read operations to that just sufficient for the required frames and channels. The important measure is that the cost of indexing, computing and executing seek/read operations does not outweigh the reduction in data read.

For example if a frame has 40 channels and only 5 are required then, if the cost per byte stays the same then the user sees a 8 fold speed improvement. If the cost per byte doubles then the user still sees a 4 fold speed improvement. If

the cost per byte rises 8 fold there is no advantage over doing a sequential read of all channels. Beyond an eight fold rise in indexing cost the user sees a performance *reduction*.

A: All Frames, all Channels

This is the baseline, indexing plays no part as this is a straightforward sequential read operation of every channel in every frame.




Although there is quite a spread there is, gratifyingly, no obvious trend for the cost to increase as the file size does which would indicate worse than $O(N)$ behaviour. The behaviour is clearly $O(N)$. The cost in ms/Mb is:

| A: | Cost ms/Mb |
|---------|------------|
| Minimum | 541.8 |
| Mean | 1446.9 |
| Maximum | 4003.3 |

C: Adjacent Frames and Channels

This is taking a random, but sequential, subset of the frames and a random, but sequential, subset of the channels. This requires the indexer to do a logical seek operation to the start of the frames then, within each frame a seek then read then seek operation.

The results are plotted compared to the baseline and the ratio of the cost of C relative to the cost of A for each file is plotted on the right hand axis.



The cost in ms/Mb is:

| Value | A: Cost ms/Mb | C: Cost ms/Mb | Ratio C/A |
|-------------|---------------|---------------|-------------|
| Minimum | 541.8 | 545.7 | 0.57 |
| Mean | 1446.9 | 1561.3 | 1.13 |
| Maximum | 4003.3 | 4485.8 | 4.25 |


This means that a small increase in cost (13%) is the price of a hugely reduced data set.

D: Adjacent Frames, any Channels

This is taking a random, but sequential, subset of the frames and a random, but non-sequential, subset of the channels. This requires the indexer to do a logical seek operation to the start of the frames then, within each frame multiple seek/read operations.

This is highly representative of the indexing operation performed when plotting, say, any 200 foot section of a number of selected channels.

The results are plotted compared to the baseline and the ratio of the cost of D relative to the cost of A for each file is plotted on the right hand axis.



The cost in ms/Mb is:

| Value | A: Cost ms/Mb | D: Cost ms/Mb | Ratio D/A |
|-------------|---------------|---------------|-------------|
| Minimum | 541.8 | 581.8 | 0.98 |
| Mean | 1446.9 | 3410.5 | 2.55 |
| Maximum | 4003.3 | 11928.6 | 7.44 |

It should be noted that this test is deliberately harsh in that non-sequential channels are always chosen. If some of the channels are adjacent then the cost reduces, for those channels, more towards C (typically half the cost of D).


Even so provided the number of channels of interest is less than 40% of the total indexing this way provides a real speed improvement. The important point being this may not produce an improvement (and may actually be slower) for small frame sizes; they are not the problem precisely because they are small. For the seriously problematic large frame sizes then indexing will always be faster, often dramatically so.

E: Any Frames, any Channels

This is taking a random, non-sequential, subset of the frames and a random, but non-sequential, subset of the channels. This requires the indexer to perform a set of logical seek/read operations to each frame then, within each frame multiple seek/read operations.

Essentially this is the same as test D but skipping intermediate frames.

The results are plotted compared to the baseline and the ratio of the cost of E relative to the cost of A for each file is plotted on the right hand axis.




The cost in ms/Mb is:

| Value | A: Cost ms/Mb | E: Cost ms/Mb | Ratio E/A |
|-------------|---------------|---------------|-------------|
| Minimum | 541.8 | 619.9 | 1.03 |
| Mean | 1446.9 | 3491.7 | 2.57 |
| Maximum | 4003.3 | 13552.5 | 7.98 |

There is a very slight (around 1-5%) additional cost over D but the huge benefit is being able to skip intermediate frames. This means that a low resolution plot (say 1:500) of a high resolution log (say sampling every 1.2 inches) could read every fifth frame (six inch sampling) and that would be plotted every 0.012" (say 1 pixel) as a speedup of almost 500%.

All Measurements

For the sake of completeness, here are all the results:



Performance Improvements

The low level performance of TotalDepth is pretty good. FrameSet performance is satisfactory. Further improvement is certain for *Indexing Performance Improvements* once the existing C code (in another project) is integrated into this one.

Populating the frame is a costly exercise and the current solution takes this path:

```
File bytes -> Cython convert to C double -> convert to Python float -> insert into a
↳ numpy array.
```

All this boxing and unboxing is expensive and a faster (but with more code complexity) is to populate the numpy array directly so this all happens in C code:

```
File bytes -> Convert to C double -> copy directly into numpy memory space
```

This should provide a great speedup.

The SVG creation is also worth looking at.

1.9.3 Plotting Wireline Data

Aside from the LogPass (the data structure that holds the frame data) the plot layout needs to be specified. There are two ways that TotalDepth does this:

- A plot specification that is *integral* to the file. For example; LIS files may well have FILM and PRES tables within them that configure the plot as the recording engineer (or software) intended. In this case TotalDepth can make those plots directly.
- A plot specification that is specified *externally* to the file. TotalDepth supports one such way; using LgFormat XML files and these are described below.

Wireline Files With Integral Plot Data

This applies to LIS (and possibly RP66 files). The LAS file specification does not describe any plot specification at all.

LIS Plot Specification

There are a number of table-like Logical Records (type 34) within a Log Pass that can specify the plot layout. As a minimum TotalDepth.LIS needs a FILM and a PRES record.

FILM Record

A dump of a FILM Logical Record might look like this:

```
Table record (type 34) type: FILM
MNEM  GCOD  GDEC  DEST  DSCA
-----
1      EEE   ----  PF2   D200
2      E4E   -4--  PF1   DM
```

The columns are:

| Col- umn | Description |
|-------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| MNEM | The (logical) name of the output, TotalDepth uses this as part of the plot file name. |
| GCOD | The coding of the tracks. E4E means three tracks which have linear, log (4 decades), linear. With three tracks the X axis track (depth for example) appears between the first and second tracks. |
| GDEC | The number of logarithmic decades for each track, – for linear. |
| DEST | The physical destination (in the logging unit) of the plot. Ignored. |
| DSCA | The depth scale, encoded. For example D200 means 1:200. |

PRES Record

A dump of a PRES Logical Record might look like this:

```
Table record (type 34) type: PRES
MNEM  OUTP  STAT  TRAC  CODI  DEST  MODE      FILT      LEDG      REDG
-----
SP     SP     ALLO  T1     LLIN  1     SHIF      0.500000  -80.0000  20.0000
CALI   CALI   ALLO  T1     LDAS  1     SHIF      0.500000   5.00000  15.0000
```

| | | | | | | | | | |
|------|------|------|-----|------|------|------|----------|----------|---------|
| MINV | MINV | DISA | T1 | LLIN | 1 | SHIF | 0.500000 | 30.0000 | 0.00000 |
| MNOR | MNOR | DISA | T1 | LDAS | 1 | SHIF | 0.500000 | 30.0000 | 0.00000 |
| LLD | LLD | ALLO | T23 | LDAS | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| LLDB | LLD | ALLO | T2 | HDAS | 1 | GRAD | 0.500000 | 2000.00 | 200000. |
| LLG | LLG | DISA | T23 | LDAS | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| LLGB | LLG | DISA | T2 | HDAS | 1 | GRAD | 0.500000 | 2000.00 | 200000. |
| LLS | LLS | ALLO | T23 | LSPO | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| LLSB | LLS | ALLO | T2 | HSPO | 1 | GRAD | 0.500000 | 2000.00 | 200000. |
| MSFL | MSFL | ALLO | T23 | LLIN | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| 11 | DUMM | DISA | T1 | LLIN | NEIT | NB | 0.500000 | 0.00000 | 1.00000 |
| 12 | DUMM | DISA | T1 | LLIN | NEIT | NB | 0.500000 | 0.00000 | 1.00000 |
| ... | | | | | | | | | |

| Column | Description |
|--------|----------------------------------------------------------------------------------------|
| MNEM | The (logical) name of the output curve. Note multiple curves might come from one OUTP. |
| OUTP | The source of the curve. |
| STAT | Status, is this curve to be plotted. |
| TRAC | Which track the curve should be plotted on. |
| CODE | The line coding, dot, dash etc. |
| DEST | The logical film that this curve is sent to. Can be BOTH and so on. |
| MODE | What to do when the curve goes off scale (wrap round the track for example). |
| FILT | Filtering. Unused. |
| LEDG | Value of the left edge of the plot. |
| REDG | Value of the right edge of the plot. |

Records Needed for a LIS Plot

As a minimum TotalDepth needs a FILM and PRES plot, using these TotalDepth can produce a plot identical to that when the data was recorded.

In future releases TotalDepth might also support these Logical Records for plotting:

- AREA: Describes shading between curves on a plot.
- PIP: Describes integration marks on the plot such as integrated transit time, integrated hole volume etc.
- VDL: Describes presentation of waveform amplitude data.

Wireline Files With External Plot Data

This can apply to any wireline file and it means using an external configuration file to decide the plot layout. For example; LAS files do not have any plot specification (the LAS standard precludes this). The presentation of the plot is made with an external plot specification.

These external plot specifications are numerous and varied. TotalDepth currently supports one such specification: the XML *LgFormat* or *LgSchema* files.

LgFormat XML Files

These appear to originate from some of Schlumberger's "free" software.

Here is an example LgFormat XML file for plotting [HDT logs](#). TotalDepth supplies an number of examples of these.

There are a number of problems¹ with the LgFormat which is why TotalDepth only supports a subset of it while we look for something better.


Internal Plot Algorithms

This describes some algorithms used by the `Plot` module. This is for information only as these algorithms are internal and the user has little or no control over them.

Plotting the Legends (Scales)

These are at each end of the plot per curve and may span a number of tracks or be limited to half a track. Here is an example which has seven curves:

TODO: Finish this



There are two important methods that implement this algorithm: `Plot.Plot._retCurvePlotScaleOrder()` and `Plot.Plot._plotScale()`

Interpolating Backups


Industry standard wireline plots have the notion of curve backups where if the the trace for a particular curve goes off scale on one side of the track it might well reappear from the alternate side.

Here is a simulated example generated by `TestPlot.py` where a single curve (a sin curve with an amplitude of +/- 40) is plotted in full on track one. The same curve is plotted fully backed up:


- In green on track two with a scale of +/- 5

¹ For example the `LgCurve` element content of `<LeftLimit>` and `<RightLimit>` is numeric, without units. This robs a compliant implementation of the opportunity of converting frame data, say in "V/V " to plot data say "PU " which might be far more appropriate. Truth in advertising prompts me to say that LIS PRES tables have the same flaw but they have a reasonable excuse that they are *per file* specification rather than a global specification.

- In blue on track two with a scale of +/- 20
- In red on track three with a scale of +/- 2.5
- In aqua on track three with a scale of +/- 10



The algorithm that does this is probably best illustrated by example. The diagram below shows a curve (in the white track on the left) that goes from point A goes off-scale to the right to point B in 'real' space. The line A-B is subdivided by track widths and these *crossing* lines are plotted by interpolation in the track space making the line space A-B' (so-called 'FlyBack' lines are omitted in the diagram). If the *Backup Mode* is *wrap* then both red and green lines in the track are plotted. In this case if the *Backup Mode* is *1* then only the red lines are plotted in the track i.e. only one backup allowed.



On the return B-C a similar process happens in reverse.

Backup Specification

A backup specification is expected for any plot *per-curve*. Internally a backup specification is a pair of integers. If the virtual track position is less than the value (if left) or greater than the value (if right) then it is off scale. Zero is a special case in that all virtual track positions are on scale.

Various values have been predefined and there are existing mappings from LIS data and LgFormat XML files. The following table describes all of this.

| Spec. | Symbol | Description | LIS Mapping | LgFormat Mapping |
|---------|----------------|-----------------------------------------------------------------------------------------------------------------|--------------|------------------------|
| (1, -1) | BACKUP_NONE | No backup | 'NB', 'GRAD' | |
| (0, 0) | BACKUP_ALL | Every backup i.e. 'wrap' Note: Plot.py has a way of limiting ludicrous backup lines to a sensible number; say 4 | 'WRAP' | 'LG_WRAPPED', 'LG_X10' |
| (-1, 1) | BACKUP_ONSCALE | Single backup to left or right | 'SHIF' | '1' |
| (-2, 2) | BACKUP_TWICE | Two backups to left or right | | '2' |
| (-1, 1) | BACKUP_LEFT | Single backup to left only | | 'LG_LEFT_WRAPPED' |
| (1, 1) | BACKUP_RIGHT | Single backup to right only | | 'LG_RIGHT_WRAPPED' |

Note that it is also common to have one curve with no backup and a second curve driven from the same output with a different scale acting as a backup. This has the advantage that a different coding and colour can be assigned to it. See [Plotting the Legends \(Scales\)](#) above for an example with a Laterlog plot.

Algorithm

The backup algorithm works as follows:

- For every point plotted an integer wrap value is calculated.
- If the wrap value is different from the previous wrap value then some interpolation is required and the `Plot._interpolateBackup()` method is called (below).
- Otherwise the point is plotted.

`_interpolateBackup`

The `Plot._interpolateBackup()` method manages all the different cases where a backup is needed given the backup configuration. It relies on `Plot._retInterpolateWrapPoints()` to generate a list of interpolated lines, including *crossing lines*, between one point and another.

`_filterCrossLineList`

A further refinement to the algorithm is limiting the number of *crossing lines*. Consider the SP curve represented by this data taken from a real example:

| Depth (ft) | SP (mV) |
|------------|--------------|
| 10245.0 | 332.724 |
| 10245.5 | 13716948.000 |
| 10246.0 | 41150204.000 |
| 10246.5 | 68583456.000 |
| 10247.0 | 96016712.000 |
| 10247.5 | 334.176 |

Clearly some episode happened between 10245.0 and 10245.5 feet that caused a jump of 13716615.276 mV. This could have been an recording disturbance (unlikely as where would you find 96kV at 10247 feet?) or an editing error. In any case on a scale of -20 to 80 mV means 137,166 (mostly spurious) wrap lines crossing the track. This can turn a 1.6Mb file into a 91Mb file! To stop this a arbitrary limit is made to the number of *crossing lines* (e.g. 4) between each Xaxis interval. This limit filters the *crossing line* list to an evenly distributed list of 4 (or thereabouts).

The method that does this is The `Plot._filterCrossLineList()` method

1.9.4 TotalDepth and SaaS

This design shows the potential for running TotalDepth as *Software as a Service* (SaaS) or, if you prefer, *Cloud Computing*.

The design envisages a server running the full TotalDepth software and any number of clients running sub-sets of that software. Client software could be in-browser or on-device.

Network speed (i.e. latency+bandwidth) is crucial to the performance of this system and the network connection between the client and the server could be any of these (in order of slowness):

- A client and a server both running on the client's machine.
- A client device and a server running on a high speed LAN.
- A client device communicating with a server via a VPN.
- A client device communicating with a remote server via the internet.

TotalDepth accommodates all of these.

Processing Server Side Files


There is no particular challenge here as the server has all it needs to process any client instruction. The big disadvantage is that the client has to upload the file to the server before they can do anything. For small jobs on large files that can impose an disproportionate cost.

Processing Files that Remain on the Client's Device

The real challenge is: the client has a (very large?) file and wants to do something small (or at least incremental) with it, for example “Plot curves XYZ from 5840 to 5600 feet using format ABC” and the server only needs a tiny fraction of that file. Regardless of the network connection there should be some cunning in extracting the data that the client needs in minimal time. TotalDepth’s indexing technique makes this possible.

This design shows how the client can work with the server without the tedious business of the client having to upload the complete file to the server. Instead the client and server cooperate to make sure that the minimum data is transferred for the immediate task in hand.

The design is illustrated below, the client is on the left:



Starting the session

The session is initialised by the user requesting the client to operate on a particular file on the clients device. The client passes basic file information to the server and receives a unique session ID.

The Session ID

The session ID could be a portable file ID, such as a checksum. Thus two users using the same file could benefit from each others read transactions. This would require copy-on-write and session ID modification.

Another optimisation when using a checksum is that if the server already has an exact copy of the file (using the checksum as a proxy for that) then the server could provide data from its own copy of the file without the user having to transfer any data to the server at all.

Session Bootstrapping

Given a valid session ID the client code reads the minimum structural information for the server to comprehend (and mirror) the file structure. This will vary according to the file format (and will vary according to file size).

LIS

The client code must be capable of processing TIF markers, Physical Record headers and trailers and Logical Record headers. The client passes this data as an ordered list of pairs `[(tell, bytes), ...]` where `tell` is the `size_t` position in the of the Physical Record (or TIF marker) that starts the Logical Record and `bytes` is the raw two bytes of the Logical Record Header.

LAS

As LAS files are small and do not lend themselves easily to efficient indexing then, most likely, it is worth passing the entire client file to the server.

RP66

This will be similar to LIS bootstrapping with the client code processing Visible Record Headers and Logical Record segments.

Index Completion

The bootstrap information passed to the server allows the server to construct a virtual, partial, logical image of the file. The server may request further information in the form of an ordered list of pairs `[(file position, number of bytes), ...]`. The client does a series of seek/read operations and passes the data back to the server as a list of pairs `[(file position, bytes), ...]`. This allows the server to complete the file index.

The total size of the data transferred to the server at this stage is typically 0.6% of the file size. See [Indexing LIS Files](#) for a description of how LIS files are indexed and [Multi-Processing](#) for a study of index sizes.

Rest of Session

Once bootstrapped any user request is passed by the client to the server, for example: “Plot curves ABC from 5840 to 5600 feet”.

The server then consults its virtual file image to see if it has the data to satisfy the request. If so then the result of the request is sent to the client.

If the server does not have sufficient data in its virtual file image then the server will send to the client an (ordered) list of pairs [(file position, number of bytes), ...]. The client does a series of seek/read operations on each pair and passes the data back to the server as a list of pairs [(file position, bytes), ...]. The server adds these to its virtual file image. The server then can complete the request.

Over time the virtual file image would grow but only as fast as the user's (new) demands.

Data Persistence

It is possible for the server to persist the virtual file image over any number of sessions, this would improve the performance even further.

SaaS Pros and Cons

Advantages

- Low barrier to use: browser based, no installation.
- Cross Platform: desktop, tablet, mobile etc.
- Minimum client code.
- Continuous software version update from the server.
- Integrated with other Internet services for example mapping data.
- Tailored appearance per client.
- Cloud availability behind the server.
- All usage data is available on server logs.

Disadvantages

- Requires network connection (could have a server version running locally).
- User agent variability.
- Speed/performance limited by network.
- Server infrastructure and investment.
- Continuous maintenance and support.
- Security.

1.10 TotalDepth and Software Test

Contents:

1.10.1 Unit Tests

This describes how unit testing is done in TotalDepth.

Module Unit Testing

Most modules have their unit tests in the `test/` directory in the package the module is in. The test code is usually in `TestModule.py`.

Example

For the module `TotalDepth.LIS.core.LogPass` the unit tests are in `TotalDepth/LIS/core/test/TestLogPass.py` and they can be run thus:

```
$ cd <TOTALDEPTH>/src/TotalDepth/LIS/core
$ python3 test/TestLogPass.py
```

The output is:

```
TestClass.py script version "0.8.0", dated 10 Jan 2011
Author: Paul Ross
Copyright (c) Paul Ross

testSetUpTearDown (__main__.TestLogPass_LowLevel)
TestLogPass_LowLevel: Tests setUp() and tearDown(). ... ok
test_00 (__main__.TestLogPass_LowLevel)
TestLogPass_LowLevel.test_00(): Construction. ... ok
test_01 (__main__.TestLogPass_LowLevel)

... 8<----- Many lines snipped ----->8

TestLogPass_UpIndirect.test_02(): 3 LR, 5 fr, 4 ch. setFrameSet() theFrSl=slice(2,4,
↪2). ... ok
test_03 (__main__.TestLogPass_UpIndirect)
TestLogPass_UpIndirect.test_03(): 3 LR, 5 fr, 4 ch. setFrameSet() theFrSl=slice(1,5,
↪2). ... ok
test_10 (__main__.TestLogPass_UpIndirect)
TestLogPass_UpIndirect.test_10(): genFrameSetHeadings() ... ok

-----
Ran 54 tests in 0.271s

OK
CPU time =    0.275 (S)
Bye, bye!
```

Package Unit Testing

Most packages have their unit tests in the `test/UnitTests.py` in the package the module is in.

Example

For the module `TotalDepth.LAS.core` the unit tests are in `TotalDepth/LAS/core/test/UnitTests.py` and they can be run thus:

```
$ python3 test/UnitTests.py
```

And the result is:

```

UnitTests.py script version "0.8.0", dated 2009-09-15
Author: Paul Ross
Copyright (c) Paul Ross

Command line:
test/UnitTests.py

('File:', 'test/UnitTests.py')
Testing TestEngVal
-----
Ran 55 tests in 0.002s

OK

8<----- Many lines snipped ----->8

OK
Testing TestUnits
Time:      0.952 rate      102.547 k/S Time:      0.389 rate      250.863 k/S Time:      0.175_
↪rate      556.827 k/S -----
↪-----
Ran 8 tests in 1.517s

OK
Results
  Tests: 803
  Errors: 0
Failures: 0

CPU time = 215.986 (S)
Bye, bye!

```

Unit Testing and coverage

Ned Batchelor's *excellent* coverage tool can be used with these unit tests:

```
$ coverage run test/TestMnem.py
```

And the result is:

```

TestMnem.py script version "0.8.0", dated May 26, 2011
Author: Paul Ross
Copyright (c) 2011 Paul Ross.

test_00 (__main__.TestMnem)
TestMnem.test_00(): Tests setUp() and tearDown(). ... ok
test_01 (__main__.TestMnem)
TestMnem.test_01(): Basic constructor. ... ok
test_02 (__main__.TestMnem)
TestMnem.test_02(): Truncation of >4 chars. ... ok
test_03 (__main__.TestMnem)
TestMnem.test_03(): Padding of <4 chars. ... ok
...
test_70 (__main__.TestMnem)
TestMnem.test_70(): Construction with a string. ... ok

```

```
-----
Ran 21 tests in 0.002s
```

```
OK
CPU time =    0.003 (s)
Bye, bye!
```

Reporting coverage:

```
$ coverage report -m
```

And the result is:

| Name | Stmts | Miss | Cover | Missing |
|----------------------------------------|-------|------|-------|--------------------------|
| ----- | | | | |
| ↪----- | | | | |
| TotalDepth/src/TotalDepth/LIS/__init__ | 7 | 0 | 100% | |
| TotalDepth/src/TotalDepth/__init__ | 6 | 0 | 100% | |
| Mnem | 52 | 0 | 100% | |
| __init__ | 0 | 0 | 100% | |
| test/TestMnem | 161 | 13 | 92% | 259, 286-289, 292-296, ↪ |
| ↪298-300 | | | | |
| ----- | | | | |
| ↪----- | | | | |
| TOTAL | 226 | 13 | 94% | |

1.10.2 Testing the Plot Package

This is a comprehensive testing of your installation to see if LIS/LAS files can be written, read and plotted. The code writes specific LIS/LAS files in memory, reads them back with the appropriate parser then plots them as SVG files.

Running the test

TestPlot is a unit test which also has performance tests within it. It is invoked thus:

```
$ python tests/unit/test_util/test_plot/TestPlot.py
```

The response should be something like:

```
TestClass.py script version "0.1.0", dated 2010-08-02
Author: Paul Ross
Copyright (c) Paul Ross

test_00 (__main__.TestPlotRollStatic)
TestPlotRollStatic.test_00(): Tests setUp() and tearDown(). ... ok
test_01 (__main__.TestPlotRollStatic)
TestPlotRollStatic.test_01(): viewBox. ... ok

... 8<----- snip, snip, snip ----->8

test_01 (__main__.TestPlotReadLIS_SingleSinCurve) ... ExecTimerList [6]:
  Loading FrameSet          Size:    0.002 (MB) Time:    0.010 (s) Cost:   3838.393_
  ↪(ms/MB)
  Initialising LIS plot     Size:    0.000 (MB) Time:    0.001 (s) Cost:         N/A_
  ↪(ms/MB)
```

```

Plotting Tracks          Size:    0.000 (MB) Time:    0.005 (s) Cost:    N/A_
↪ (ms/MB)
Plotting XGrid          Size:    0.000 (MB) Time:    0.023 (s) Cost:    N/A_
↪ (ms/MB)
Plotting scales (legends) Size:    0.000 (MB) Time:    0.013 (s) Cost:    N/A_
↪ (ms/MB)
Plotting curves          Size:    0.002 (MB) Time:    0.141 (s) Cost:    9338.957_
↪ (ms/MB) ok
test_00 (__main__.TestPlotReadLIS_SingleSquareCurveLowFreq)
TestPlotReadLIS_SingleSquareCurve.test_00(): Tests setUp() and tearDown(). ... ok

... 8<----- snip, snip ----->8

test_12 (__main__.TestPlotReadLAS_XML_LgFormat)
TestPlotReadLAS_XML_LgFormat.test_12(): Plot from XML LgFormat files - density,
↪ porosity and multiple gamma ray curves. ... ExecTimerList [6]:
  Initialising LAS plot: "Porosity_GR_3Track" Size:    0.000 (MB) Time:    0.001 (s)
↪ Cost:    N/A (ms/MB)
  Plotting API Header          Size:    0.000 (MB) Time:    0.016 (s)
↪ Cost:    N/A (ms/MB)
  Plotting Tracks              Size:    0.000 (MB) Time:    0.005 (s)
↪ Cost:    N/A (ms/MB)
  Plotting XGrid               Size:    0.000 (MB) Time:    0.055 (s)
↪ Cost:    N/A (ms/MB)
  Plotting scales (legends)    Size:    0.000 (MB) Time:    0.013 (s)
↪ Cost:    N/A (ms/MB)
  Plotting curves              Size:    0.020 (MB) Time:    0.096 (s)
↪ Cost:    5009.433 (ms/MB) ok

-----
Ran 107 tests in 34.318s

OK
CPU time = 34.179 (S)
Bye, bye!

```


The important thing is that there should be no reported failures.

Results

You should find in the directory `<TOTALDEPTH>/tests/unit/test_util/test_plot/test_svg` a set of test plots.

Index

This directory has an `<TOTALDEPTH>/tests/unit/test_util/test_plot/test_svg/index.html` that looks like this:

 file://localhost/Users/paulross/Documents/workspace/TotalDepth/src/TotalDepth/util/plot/test_s...

API Headers

1. [link](#) TestLogHeaderLIS.test_05(): Empty API header from LIS data (upright).
2. [link](#) TestLogHeaderLIS.test_06(): Empty API header from LIS data (rotated).
3. [link](#) TestLogHeaderLIS.test_10(): API header with CONS information from LIS data (upright).
4. [link](#) TestLogHeaderLIS.test_11(): API header with CONS information from LIS data (rotated).
5. [link](#) TestLogHeaderLAS.test_05(): Empty API header from LAS data (upright).
6. [link](#) TestLogHeaderLAS.test_06(): Empty API header from LAS data (rotated).
7. [link](#) TestLogHeaderLAS.test_10(): API header with CONS information from LAS data (upright).
8. [link](#) TestLogHeaderLAS.test_11(): API header with CONS information from LAS data (rotated).

Plots from LIS files

1. [link](#) TestPlotReadLIS_SingleSinCurve.test_01(): Sinusoidal SP plotted on a number of different scales.
2. [link](#) TestPlotReadLIS_SingleSquareCurveLowFreq.test_01(): Square wave with 4' spacing to check wrap interpolation.
3. [link](#) TestPlotReadLIS_SingleSquareCurveHighFreq.test_01(): Square wave with 0.5' spacing to check wrap interpolation.
4. [link](#) TestPlotReadLIS_HDT.test_01(): 200 feet of HDT.
5. [link](#) TestPlotReadLIS_SuperSampled.test_01(): Channels at 4' frame spacing, single, x8, x32 super-sampling.
6. [link](#) TestPlotReadLIS_COLO_Named.test_01(): Sinusoidal SP plotted on a number of different named colours.
7. [link](#) TestPlotReadLIS_COLO_Numbered.test_01(): Numbered colours 400 (red), 040 (green), 004 (blue).
8. [link](#) TestPlotReadLIS_COLO_Numbered_Comp.test_01(): Numbered colours 440 (yellow), 404 (magenta), 044 (cyan).
9. [link](#) TestPlotReadLIS_Perf_00.test_01(): Film 1 2000' of 10 curves, linear scale.
10. [link](#) TestPlotReadLIS_Perf_00.test_02(): Film 2 2000' of 10 curves, linear and log scale.
11. [link](#) LgFormat: "Triple_Combo_00" 2000 of 10 curves, linear and log scale.
12. [link](#) LgFormat: "Resistivity_3Track_Logrithmic.xml_00" 2000' of 10 curves, linear and log scale.
13. [link](#) TestPlotReadLIS_SingleSinCurve.test_01(): Sinusoidal SP plotted on a number of different scales with API header.


Plots from LAS files

1. [link](#) LgFormat: "Triple_Combo" 200 of 15 curves, linear and log scale from LAS file, DOWN log, no header.
2. [link](#) LgFormat: "Resistivity_3Track_Logrithmic.xml" 200' of 15 curves, linear and log scale from LAS file, DOWN log, no header.
3. [link](#) LgFormat: "Triple_Combo" 200 of 10 curves, linear and log scale from LAS file, DOWN log, with header.
4. [link](#) LgFormat: "Resistivity_3Track_Logrithmic.xml" 200' of 15 curves, linear and log scale from LAS file, DOWN log, with header.
5. [link](#) LgFormat: "Triple_Combo" 200 of 15 curves, linear and log scale from LAS file, UP log, no header.
6. [link](#) LgFormat: "Resistivity_3Track_Logrithmic.xml" 200' of 15 curves, linear and log scale from LAS file, UP log, no header.
7. [link](#) LgFormat: "Triple_Combo" 200 of 15 curves, linear and log scale from LAS file, UP log, with header.
8. [link](#) LgFormat: "Resistivity_3Track_Logrithmic.xml" 200' of 15 curves, linear and log scale from LAS file, UP log, with header.
9. [link](#) LgFormat: "Triple_Combo" 1000 of 15 curves, linear and log scale from LAS file, large down log, with header.
10. [link](#) LgFormat: "Resistivity_3Track_Logrithmic.xml" 1000' of 15 curves, linear and log scale from LAS file, large down log, with header.
11. [link](#) LgFormat: "Triple_Combo" 100 feet of 5 gamma ray curves.
12. [link](#) LgFormat: "Resistivity_3Track_Logrithmic.xml" 100 feet of 5 gamma ray curves.
13. [link](#) LgFormat: "Porosity_GR_3Track" 100 feet of Density, porosity and 5 gamma ray curves.

//

Example Plot

Navigate to a typical test LIS plot from that index such as:



Cool. If you see that then your TotalDepth installation is pretty good!

1.11 API Reference

Contents:

1.11.1 TotalDepth.LIS API Reference

Contents:

LIS Handling of Representation Codes

This describes how TotalDepth.LIS handles representation codes, it covers several modules.

Design

There is a top level module `RepCode` that imports all sub-modules and provides some fundamental definitions. Sub-modules `pRepCode` and `cRepCode` provide alternative implementations in Python or Cython.

RepCode Module

Description

This provides the main interface to Representation Code processing as well as some fundamental definitions.

This module is the top level module that imports other sub-modules implemented in Python, Cython or C/C++. The Cython implementations take precedence as this module imports the sub-modules thus:

```
from TotalDepth.LIS.core.pRepCode import *
from TotalDepth.LIS.core.cRepCode import *
```

Usage

It is designed to use thus:

```
from TotalDepth.LIS.core import RepCode
```

Reference

Module for translating raw LIS to an appropriate internal type for LIS Representation Codes ('RepCodes').

This aggregates `pRepCode` and `cRepCode` with the latter overwriting the former.

Created on 11 Nov 2010

@author: p2ross

exception `TotalDepth.LIS.core.RepCode.ExceptionRepCodeNoLength`
Exception for indeterminate length when using Rep Code 65.

exception `TotalDepth.LIS.core.RepCode.ExceptionRepCodeRead`

Exception for unknown Representation codes in look up tables.

exception `TotalDepth.LIS.core.RepCode.ExceptionRepCodeWrite`

Exception for unknown Representation codes in look up tables.

`TotalDepth.LIS.core.RepCode.read49` (*theFile*)

Returns a Representation Code 49 value from a File object.

`TotalDepth.LIS.core.RepCode.read50` (*theFile*)

Returns a Representation Code 50 value from a File object.

`TotalDepth.LIS.core.RepCode.read56` (*theFile*)

Returns a Representation Code 56 value from a File object.

`TotalDepth.LIS.core.RepCode.read66` (*theFile*)

Returns a Representation Code 66 value from a File object.

`TotalDepth.LIS.core.RepCode.read68` (*theFile*)

Returns a Representation Code 68 value from a File object.

`TotalDepth.LIS.core.RepCode.read70` (*theFile*)

Returns a Representation Code 70 value from a File object.

`TotalDepth.LIS.core.RepCode.read73` (*theFile*)

Returns a Representation Code 73 value from a File object.

`TotalDepth.LIS.core.RepCode.read77` (*theFile*)

Returns a Representation Code 77 value from a File object.

`TotalDepth.LIS.core.RepCode.read79` (*theFile*)

Returns a Representation Code 79 value from a File object.

`TotalDepth.LIS.core.RepCode.readBytes` (*theRc, theB, theLen=None*)

Reads a Representation Code from the a bytes() object. If theRc is 65 (string) then theLen must be supplied, up to that length of bytes will be returned.

`TotalDepth.LIS.core.RepCode.readBytes130` (*by*)

Reads Dipmeter RepCode 130 and returns a list of (integer) values.

`TotalDepth.LIS.core.RepCode.readBytes234` (*by*)

Reads Dipmeter RepCode 234 and returns a list of (integer) values.

`TotalDepth.LIS.core.RepCode.readBytes49` (*arg*)

Returns a Representation Code 49 value from a bytes object.

`TotalDepth.LIS.core.RepCode.readBytes50` (*arg*)

Returns a Representation Code 50 value from a bytes object.

`TotalDepth.LIS.core.RepCode.readBytes56` (*arg*)

Returns a Representation Code 56 value from a bytes object.

`TotalDepth.LIS.core.RepCode.readBytes66` (*arg*)

Returns a Representation Code 66 value from a bytes object.

`TotalDepth.LIS.core.RepCode.readBytes68` (*arg*)

Returns a Representation Code 68 value from a bytes object.

`TotalDepth.LIS.core.RepCode.readBytes70` (*arg*)

Returns a Representation Code 70 value from a bytes object.

`TotalDepth.LIS.core.RepCode.readBytes73` (*arg*)

Returns a Representation Code 73 value from a bytes object.

`TotalDepth.LIS.core.RepCode.readBytes77 (arg)`

Returns a Representation Code 77 value from a bytes object.

`TotalDepth.LIS.core.RepCode.readBytes79 (arg)`

Returns a Representation Code 79 value from a bytes object.

`TotalDepth.LIS.core.RepCode.readRepCode (theRc, theFile, theLen=None)`

Reads a Representation Code from the file and returns a value. If theRc is 65 (string) then theLen must be supplied, up to that length of bytes will be returned.

`TotalDepth.LIS.core.RepCode.writeBytes (v, r)`

Takes a value v and a Representation Code r and converts this to a bytes() object.

`TotalDepth.LIS.core.RepCode.writeBytes66 (v)`

Converts a value to a Rep Code 66 and returns the bytes.

`TotalDepth.LIS.core.RepCode.writeBytes68 (v)`

Converts a value to a Rep Code 68 and returns the bytes.

`TotalDepth.LIS.core.RepCode.writeBytes73 (v)`

Converts a value to a Rep Code 73 and returns the bytes.

pRepCode Module

This contains Python implementations.

Usage

This module is not designed to be imported directly, use `RepCode` instead. This module can be imported only for test purposes thus:

```
from TotalDepth.LIS.core import pRepCode
```

Reference

Python module for translating raw LIS to an appropriate internal type for LIS Representation Codes ('RepCodes').

Created on 11 Nov 2010

@author: p2ross

exception `TotalDepth.LIS.core.pRepCode.ExceptionRepCode`

Specialisation of exception for Representation codes.

exception `TotalDepth.LIS.core.pRepCode.ExceptionRepCodeUnknown`

Specialisation of exception for unknown Representation codes.

`TotalDepth.LIS.core.pRepCode.from49 (theWord)`

Returns a double from Rep code 49 0x31, 16bit floating point representation. Value +153 is 0100 1100 1000 1000 or 0x4C88. Value -153 is 1011 0011 1000 1000 or 0xB388.

`TotalDepth.LIS.core.pRepCode.from50 (theWord)`

Returns a double from Rep code 0x32, 32bit floating point representation. Value +153 is 0x00084C80 Value -153 is 0x0008B380

`TotalDepth.LIS.core.pRepCode.from56 (theWord)`

Returns an integer from Rep code 0x38, signed char representation.

`TotalDepth.LIS.core.pRepCode.from66` (*theWord*)
Returns a Rep code 0x42, unsigned byte from theWord, expected to be an integer.

`TotalDepth.LIS.core.pRepCode.from68` (*theWord*)
Returns a double from a Rep code 68 word (a 32 bit integer).

`TotalDepth.LIS.core.pRepCode.from70` (*theWord*)
Returns a double from a Rep code 0x46, 32bit fixed point.

`TotalDepth.LIS.core.pRepCode.from73` (*theWord*)
Returns a integer from a Rep code 0x49, 32bit signed integer.

`TotalDepth.LIS.core.pRepCode.from77` (*theWord*)
Returns a Rep code 0x4D, 8bit mask from theWord, expected to be an integer.

`TotalDepth.LIS.core.pRepCode.from79` (*theWord*)
Returns an integer from Rep code 0x4F, 16bit signed integer.

`TotalDepth.LIS.core.pRepCode.isInt` (*r*)
Returns True if the Rep Code is represented by an integer.

`TotalDepth.LIS.core.pRepCode.lisSize` (*r*)
Returns the size in bytes for a single instance of a representation code. Zero means variable length. May raise `ExceptionRepCodeUnknown`.

`TotalDepth.LIS.core.pRepCode.maxValue` (*r*)
Returns the maximum value for various representation codes. May raise `ExceptionRepCodeUnknown`.

`TotalDepth.LIS.core.pRepCode.minMaxValue` (*r*)
Returns a pair; (minimum value, maximum value) for various representation codes. May raise `ExceptionRepCodeUnknown`.

`TotalDepth.LIS.core.pRepCode.minValue` (*r*)
Returns the minimum value for various representation codes. May raise `ExceptionRepCodeUnknown`.

`TotalDepth.LIS.core.pRepCode.read49` (*theFile*)
Returns a Representation Code 49 value from a File object.

`TotalDepth.LIS.core.pRepCode.read50` (*theFile*)
Returns a Representation Code 50 value from a File object.

`TotalDepth.LIS.core.pRepCode.read56` (*theFile*)
Returns a Representation Code 56 value from a File object.

`TotalDepth.LIS.core.pRepCode.read66` (*theFile*)
Returns a Representation Code 66 value from a File object.

`TotalDepth.LIS.core.pRepCode.read68` (*theFile*)
Returns a Representation Code 68 value from a File object.

`TotalDepth.LIS.core.pRepCode.read70` (*theFile*)
Returns a Representation Code 70 value from a File object.

`TotalDepth.LIS.core.pRepCode.read73` (*theFile*)
Returns a Representation Code 73 value from a File object.

`TotalDepth.LIS.core.pRepCode.read77` (*theFile*)
Returns a Representation Code 77 value from a File object.

`TotalDepth.LIS.core.pRepCode.read79` (*theFile*)
Returns a Representation Code 79 value from a File object.

`TotalDepth.LIS.core.pRepCode.to49 (theVal)`
Converts a double to Rep code 49 0x31, 16bit floating point representation. Value +153 is 0100 1100 1000 1000 or 0x4C88. Value -153 is 1011 0011 1000 1000 or 0xB388.

`TotalDepth.LIS.core.pRepCode.to50 (theVal)`
Converts a double to Rep code 0x32, 32bit floating point representation.

`TotalDepth.LIS.core.pRepCode.to56 (theVal)`
Converts a double to Rep code 0x38, signed char representation.

`TotalDepth.LIS.core.pRepCode.to66 (theVal)`
Converts theVal to representation code 66 integer from theWord.

`TotalDepth.LIS.core.pRepCode.to68 (v)`
Returns Representation code 68 as a 32 bit integer from a double.

`TotalDepth.LIS.core.pRepCode.to70 (v)`
Returns Rep code 0x46, 32bit fixed point from an int or double.

`TotalDepth.LIS.core.pRepCode.to73 (v)`
Returns Rep code 0x49, 32bit signed integer from an int or double.

`TotalDepth.LIS.core.pRepCode.to77 (theVal)`
Converts theVal to Rep code 0x4D, 8bit mask from theVal.

`TotalDepth.LIS.core.pRepCode.to79 (theVal)`
Converts a double to Rep code 0x4F, 16bit signed integer.

`TotalDepth.LIS.core.pRepCode.wordLength (r)`
Returns the word length in bytes used by a representation code. NOTE: This is subtly different from lisSize as it take into account dipmeter sub-channels Zero means variable length. May raise ExceptionRepCodeUnknown.

cRepCode Module

This contains Cython implementations. By the import mechanism used by RepCode these implementations take precedence over the implementations in pRepCode.

Usage

This module is not designed to be imported directly, use RepCode instead. This module can be imported only for test purposes thus:

```
from TotalDepth.LIS.core import cRepCode
```

Reference

Cython module for translating raw LIS to an appropriate internal type for LIS Representation Codes ('RepCodes'). Internal types are double, int or string.

Testing

The unit tests are in `test/TestRepCode.py` and `test/TestRepCode68.py`.

Units

Provides unit conversion for LIS79.

The `__RAW_UNIT_MAP` is the master map from which all other data is derived. Its format is as follows:

key - The unit category as four bytes representing uppercase ASCII characters. value - A tuple of three fields:

- [0] - Descriptive string of the unit category.
- [1] - The base unit name as four bytes representing uppercase ASCII characters.
- [2] - A tuple the contents of which is a four or five item tuple:
 - If four members:
 - * [2][0] - The unit name as four bytes representing uppercase ASCII characters.
 - * [2][1] - The multiplier as a float.
 - * [2][2] - Descriptive string of the units.
 - * [2][3] - **The unit name that this is an alternate for as four bytes** representing uppercase ASCII characters, or four spaces.
 - If five members:
 - * [2][0] - The unit name as four bytes representing uppercase ASCII characters.
 - * [2][1] - The multiplier as a float.
 - * [2][2] - The offset as a float.
 - * [2][3] - Descriptive string of the units.
 - * [2][4] - **The unit name that this is an alternate for as four bytes** representing uppercase ASCII characters or four spaces.

The unit name should also be unique.

TODO: Clean up units by making reciprocal e.g. 1/6.0 rather than 0.166666...

TODO: Check each unit for errors.

exception `TotalDepth.LIS.core.Units.ExceptionUnits`
Specialisation of exception for Unit conversion.

exception `TotalDepth.LIS.core.Units.ExceptionUnitsMismatchedCategory`
When a two units do not exist in the same category.

exception `TotalDepth.LIS.core.Units.ExceptionUnitsNoUnitInCategory`
When a unit does not exist in a category.

exception `TotalDepth.LIS.core.Units.ExceptionUnitsUnknownCategory`
When a unit category does not exist.

exception `TotalDepth.LIS.core.Units.ExceptionUnitsUnknownUnit`
When a unit does not exist.

class `TotalDepth.LIS.core.Units.UnitConvert` (*tup*)
Internal data structure for this module that represents a particular unit of measure. Takes a 4 or 5 member tuple from `__RAW_UNIT_MAP`.

convert (*val, other*)
Convert a value from me to the other where other is a UnitConvert object.

class TotalDepth.LIS.core.Units.**UnitConvertCategory** (*theCat, theDesc, theBaseUnitName, theUnitS*)

Internal module data structure that represents a category of units such as linear length.

theCat is the unit category.

theDesc is the description of that category.

theBaseUnitName is the name of the base units for the category. For example for linear length this is b'M'.

theUnitS is a list of unit names.

convert (*v, u_1, u_2*)

Returns a value converted from one units to another. e.g. convert(1.2, "FEET", "INCH")

unitConvertor (*u*)

Returns a UnitConvert object corresponding to the name u. Will raise a ExceptionUnitsNoUnitInCategory if not found.

units ()

Returns a list of unit names for this category.

TotalDepth.LIS.core.Units.**category** (*unit*)

Returns the category of the unit. May raise a ExceptionUnitsUnknownUnit.

TotalDepth.LIS.core.Units.**categoryDescription** (*theCat*)

Returns the description of a unit category.

TotalDepth.LIS.core.Units.**convert** (*v, u_1, u_2*)

Returns a value converted from one units to another. e.g. convert(1.2, b"FEET", b"INCH").

Will raise an ExceptionUnitsUnknownUnit if either unit is unknown.

Will raise an ExceptionUnitsMismatchedCategory if both units do not belong to the same unit category.

TotalDepth.LIS.core.Units.**hasUnit** (*u*)

Returns True if I have that unit e.g. b"FEET".

TotalDepth.LIS.core.Units.**hasUnitCategory** (*c*)

Returns True if I have that unit category e.g. b"TIME".

TotalDepth.LIS.core.Units.**opticalUnits** (*u*)

If possible returns the 'optical' units i.e. user friendly units. For example the 'optical' units of b'.1IN' are b'FEET'. Failure returns the argument.

TotalDepth.LIS.core.Units.**realUnitName** (*u*)

Returns the real unit name or None if u is the 'real' unit e.g. the 'real' unit name for b"FT" is b"FEET". May raise a ExceptionUnits or descendent.

TotalDepth.LIS.core.Units.**retUnitConvert** (*u*)

Returns a UnitConvert object for the unit. May raise a ExceptionUnits or descendent.

TotalDepth.LIS.core.Units.**retUnitConvertCategory** (*c*)

Returns a UnitConvertCategory object for the category. May raise a ExceptionUnits or descendent.

TotalDepth.LIS.core.Units.**unitCategories** ()

Returns a list of the unit categories.

TotalDepth.LIS.core.Units.**unitDescription** (*u*)

Returns the description of the unit. e.g. Given ".1IN" returns "Tenth-inches". May raise a ExceptionUnits or descendent.

TotalDepth.LIS.core.Units.**units** (*theCat=None*)

Returns an unordered list of unit names. If category is None all unit names are returned, otherwise the unit

names for a particular category are returned. This may raise a `ExceptionUnitsUnknownCategory` if the category does not exist.

Examples

Converting bytes objects:

```
from TotalDepth.LIS.core import Units

v = Units.convert(1.0, b"M", b"FEET")
# v is now 3.281
```

Testing

The unit tests are in `test/TestUnits.py`.

EngVal

This module handles engineering values i.e. a real numeric value associated with a unit-of-measure.

Operator Overloading

EngVals can be operated on by a real number or an other EngVal.

Addition and subtraction

The operators `+`, `-`, `+=`, `-=` work on mixed real numbers and EngVals as expected. If two EngVal objects then unit conversion is performed before the operation. If the two EngVals have units in different categories an `ExceptionUnit` will be raised.

Division

Operators `/`, `/=` are implemented.

Division of an EngVal by a real number preserves the EngVal units.

Division of an EngVal by an EngVal results in the following:

- It preserves the EngVal units if the denominator units are `DIMENSIONLESS`.
- **The result will have `DIMENSIONLESS` EngVal units if the numerator and denominator have units that are freely convertible i.e. in the same unit category.**
- An `ExceptionUnit` will be raised.

Multiplication

Operators `*`, `*=` are implemented for reals and EngVals. If an EngVal the units must be `DIMENSIONLESS`.

Notes

rval operators are implemented and this can result in type promotion. For example the result of `4.0 * EngVal(16, b'INCH')` is an `EngVal(64.0, b'INCH')`.

Created on 24 Nov 2010

EngVal Reference

class `TotalDepth.LIS.core.EngVal.EngVal` (*theVal, theUom=Mnem(b'x00x00x00x00')*)

Represents an engineering value that consists of a numeric value and a unit of measure (usually a string).

`__add__` (*other*)

Overload self+other, returned result has the sum of self and other. other can be an EngVal or a Real number. The units chosen are self's.

`__eq__` (*other*)

True if self == other False otherwise. If other is an EngVal unit conversion is performed which may raise an ExceptionUnit. If other is a real number then self units are ignored.

`__ge__` (*other*)

True if self >= other False otherwise. If other is an EngVal unit conversion is performed which may raise an ExceptionUnit. If other is a real number then self units are ignored.

`__gt__` (*other*)

True if self > other False otherwise. If other is an EngVal unit conversion is performed which may raise an ExceptionUnit. If other is a real number then self units are ignored.

`__iadd__` (*other*)

Addition in place, other must be a real number or an EngVal where it is converted to my units.

`__imul__` (*other*)

Overload self *= other. other must be a real number or a dimensionless EngVal.

`__isub__` (*other*)

Subtraction in place, other must be a real number or an EngVal where it is converted to my units.

`__itruediv__` (*other*)

Overload self /= other. other must be a real number or a dimensionless EngVal.

`__le__` (*other*)

True if self <= other False otherwise. If other is an EngVal unit conversion is performed which may raise an ExceptionUnit. If other is a real number then self units are ignored.

`__lt__` (*other*)

True if self < other False otherwise. If other is an EngVal unit conversion is performed which may raise an ExceptionUnit. If other is a real number then self units are ignored.

`__mul__` (*other*)

Overload self*other. other must be a real number or a dimensionless EngVal.

`__ne__` (*other*)

True if self != other False otherwise. If other is an EngVal unit conversion is performed which may raise an ExceptionUnit. If other is a real number then self units are ignored.

`__radd__` (*other*)

Right value addition, see `__add__`().

`__rmul__` (*other*)

Right value multiplication, see `__mul__`().

__rsub__ (*other*)
Right value subtraction, see **__sub__** ().

__rtruediv__ (*other*)
Right value true division, see **__truediv__** ().

__str__ ()
String representation.

__sub__ (*other*)
Overload self-other, returned result has the sum of self and other. The units chosen are self's.

__truediv__ (*other*)
Overload self/other. other must be a real number or an EngVal. If the units of other are dimensionless then treat as a real number. If the units are in the same category as me convert them and return a dimensionless EngVal.

__weakref__
list of weak references to the object (if defined)

convert (*theUnits*)
Convert my value to the supplied units in-place. May raise an ExceptionUnits.

dimensionless ()
Returns True if the measure is dimensionless.

getInUnits (*theUnits*)
Returns my value to the supplied units. May raise an ExceptionUnits.

newEngValInOpticalUnits ()
Returns a new EngVal converting me to the 'optical' units if possible. For example a value in b'.1IN' will be converted to b'FEET'.

newEngValInUnits (*theUnits*)
Returns a new EngVal converting me to the supplied units. May raise an ExceptionUnits.

pStr ()
Returns a 'pretty' ASCII string.

strFormat (*theFormat, incPrefix=True*)
Returns as as string with the value to the specified format (must be capable of handling floating point values).

class TotalDepth.LIS.core.EngVal.**EngValRc** (*theVal, theUom, theRc=None*)
An engineering value with a integer Representation Code.

__str__ ()
String representation.

encode ()
Encode my value to my RepCode returning a bytes object. May raise an ExceptionEngVal.

Mnem

Represents a MNEM (Mnemonic) as bytes. Created on May 26, 2011

@author: paulross

TotalDepth.LIS.core.Mnem.**ORDS_WS** = (32, 9, 10, 13, 11, 12)

A tuple of the ordinal values of whitespace characters

`TotalDepth.LIS.core.Mnem.ORDS_REPLACE = (0, 32, 9, 10, 13, 11, 12)`

A tuple of the ordinal values of characters that can be replaced with PAD_CHAR

`TotalDepth.LIS.core.Mnem.LEN_MNEM = 4`

Standard LIS mnemonic length

class `TotalDepth.LIS.core.Mnem.Mnem(m, len_mnem=4)`

Represents a four byte mnemonic where trailing nulls and spaces are not considered significant. This preserves original length but replaces trailing and whitespace characters with the PAD_CHAR.

m must be a bytes object or an 'ascii' str that can be converted to a bytes object.

If len_mnem is positive then m is truncated or padded as necessary to achieve that length.

If len_mnem is zero then all of m is considered significant, no padding is performed.

If len_mnem is less than zero then all characters of m are considered significant and padding up to -1*len_mnem characters of m is performed if m smaller than that.

`__init__(m, len_mnem=4)`

Constructor that prunes trailing nulls and spaces.

m

The raw bytes of the mnemonic.

`__str__()`

String representation.

pStr (*strip=False*)

Returns a 'pretty' ascii string. If strip then trailing padding is removed.

`__repr__()`

repr() representation.

`__hash__()`

Hashing, this makes bytes() and Mnem() objects interchangeable.

`__weakref__`

list of weak references to the object (if defined)

`__eq__(other)`

True if self == other False otherwise. If other is not a Mnem it is coerced into one before the comparison is made..

`__ne__(other)`

True if self != other False otherwise. If other is not a Mnem it is coerced into one before the comparison is made..

`__lt__(other)`

True if self < other False otherwise. If other is not a Mnem it is coerced into one before the comparison is made..

`__iter__()`

Byte by byte iteration.

Raw Stream Handler

The RawStream handler provides low-level stream I/O functionality.

exception `TotalDepth.LIS.core.RawStream.ExceptionRawStream`

Specialisation of exception for RawStream.

exception TotalDepth.LIS.core.RawStream.**ExceptionRawStreamEOF**

RawStream premature EOF.

class TotalDepth.LIS.core.RawStream.**RawStream** (*f, mode='rb', fileId=None*)

Class that creates a I/O stream from a file path or file-like object and provides various low level functionality on it such as unpacking.

f - A file like object or string, if the latter it assumed to be a path.

mode - The file mode, defaults to binary read.

fileId - If *f* is a string is this is present then this is used as the file name. If *f* is not a string then *f.name* is used with *fileId* as a fallback.

__init__ (*f, mode='rb', fileId=None*)

Construct with: *f* - A file like object or string, if the latter it assumed to be a path. *mode* - The file mode, defaults to binary read. *fileId* - If *f* is a string is this is present then this is used as the file name. If *f* is not a string then *f.name* is used with *fileId* as a fallback.

__enter__ ()

Context Manager support.

__exit__ (*exc_type, exc_value, traceback*)

Context manager finalisation, this closes the underlying stream.

stream

Exposes the underlying stream.

tell ()

Return the file's current position, like stdio's ftell.

seek (*offset, whence=0*)

Set the file's current position, like stdio's fseek. The *whence* argument is optional and defaults to `os.SEEK_SET` or 0 (absolute file positioning); other values are `os.SEEK_CUR` or 1 (seek relative to the current position) and `os.SEEK_END` or 2 (seek relative to the file's end). There is no return value. Not all file objects are seekable.

read (*theLen*)

Reads and returns theLen bytes.

__weakref__

list of weak references to the object (if defined)

write (*theB*)

Writes theB bytes.

close ()

Closes the underlying stream.

readAndUnpack (*theStruct*)

Reads from the stream and unpacks binary data according to the struct module format. This returns a tuple.

theStruct - A formatted instance of `struct.Struct()`.

packAndWrite (*theStruct, *args*)

Packs binary data from *args* and writes it to the stream.

theStruct - A formatted instance of `struct.Struct()`.

args - The data to write.

LIS File

Reads or writes LIS data to a physical file.

Created on 14 Nov 2010

exception TotalDepth.LIS.core.File.**ExceptionFile**

Specialisation of exception for Physical files.

exception TotalDepth.LIS.core.File.**ExceptionFileRead**

Specialisation of exception for reading Physical files.

exception TotalDepth.LIS.core.File.**ExceptionFileWrite**

Specialisation of exception for writing Physical files.

class TotalDepth.LIS.core.File.**FileBase** (*theFile, theFileId, mode, keepGoing*)

LIS file handler. This handles Physical Records (and TIF records).

class TotalDepth.LIS.core.File.**FileRead** (*theFile, theFileId=None, keepGoing=False*)

LIS file reader, this offers the caller a number of incremental read operations. This handles Physical Records (and TIF records).

theFile - A file like object or string, if the latter it assumed to be a path.

theFileId - File identifier, this could be a path for example. If None the RawStream will try and cope with it.

keepGoing - If True we do our best to keep going.

readLrBytes (*theLen=-1*)

Reads theLen LogicalData bytes and returns it or None if nothing left to read for this logical record. If theLen is -1 all the remaining Logical data is read.

skipLrBytes (*theLen=-1*)

Skips logical data and returns a count of skipped bytes. If theLen is -1 all the remaining Logical data is read.

seekCurrentLrStart ()

Setting the file position directly to the beginning of a PRH or TIF marker (if present) for the current Logical Record.

skipToNextLr ()

Skips the rest of the current Logical Data and positions the file at the start of the next Logical Record.

tellLr ()

Returns the absolute file position of the start current Logical record. This value can be safely used in seekLr.

tell ()

Returns the absolute position of the file.

ldIndex ()

Returns the index position in the current logical data.

seekLr (*offset*)

External setting of file position directly to the beginning of a PRH or TIF marker (if present). The caller is fully responsible for getting this right!

hasLd ()

Returns True if there is logical data to be read, False otherwise. NOTE: This will return False on file initialisation and only return True once the Physical Record Header (i.e. one or more logical bytes) has been read.

rewind()

Sets the file position to the beginning of file.

isEOF

True if at EOF.

unpack (*theStruct*)

Unpack some logical bytes using the supplied format. format ~ a struct.Struct object. Returns a tuple of the number of objects specified by the format or None.

```
class TotalDepth.LIS.core.File.FileWrite (theFile,           theFileId=None,           keepGo-  
                                           ing=False,   hasTif=False,   thePrLen=65535,  
                                           thePrt=<TotalDepth.LIS.core.PhysRec.PhysRecTail  
                                           object>)
```

LIS file writer. This handles Physical Records (and TIF records).

theFile - A file like object or string, if the latter it assumed to be a path.

theFileId - File identifier, this could be a path for example. If None the RawStream will try and cope with it.

keepGoing - If True we do our best to keep going.

hasTif - Insert TIF markers or not.

thePrLen - Max Physical Record length, defaults to the maximum possible length.

thePrt - Physical Records Trailer settings (defaults to PhysRec.PhysRecTail()).

write (*theLr*)

Writes the Logical Record to the file. Returns the tell() of the start of the LR.

close ()

Closes the file.

TIF Marker Handling

TIF Markers

These are 3x32bit big-endian integers at the beginning of each Physical Record.

Word[0]

This is the TIF set type, 0 for a normal TIF set. 1 for an EOF set.

Word[1]

This is the physical file location of the start of the previous set.

Word[2]

This is the physical file location of the start of the next set.

A dump looks like this:

```

      0  1  2  3  4  5  6  7  8  9  A  B  C  D  E  F
00000000: 00 00 00 00 00 00 00 00 4A 00 00 00 00 3E 00 00
00000010: 80 00 32 30 30 30 39 39 2E 44 41 54 20 20 20 20
00000020: 20 20 20 20 20 20 20 20 20 20 20 20 39 39 2F 30
00000030: 34 2F 32 39 20 20 31 30 32 34 20 20 20 20 20 20
00000040: 20 20 20 20 20 20 2E 20 20 20 00 00 00 00 00 00
00000050: 00 00 56 04 00 00 04 00 00 01 40 00 01 01 42 00
00000060: 02 01 42 00 03 04 49 00 00 02 34 04 01 42 01 05
...
00000450: 20 20 44 45 47 20 00 00 00 00 4A 00 00 00 62 08
00000460: 00 00 04 00 00 03 00 00 00 00 00 00 00 04 20 20
00000470: 00 01 44 20 20 20 20 20 31 30 41 20 20 20 20 20
...
00000860: 46 4E 00 00 00 00 56 04 00 00 6E 0C 00 00 04 00
00000870: 00 03 4F 52 20 20 20 20 20 20 20 20 20 20 20 20
...
...
...
0016E770: 18 00 BA 83 18 00 00 00 00 00 30 E5 16 00 C0 E7
0016E780: 16 00 00 3E 00 00 81 00 32 30 30 30 39 39 2E 44
...
0016E7B0: 20 20 20 20 20 20 20 20 20 20 20 20 2E 20 20 20
0016E7C0: 01 00 00 00 76 E7 16 00 CC E7 16 00 01 00 00 00
0016E7D0: C0 E7 16 00 D8 E7 16 00

```

Or:

| tell() | TIF type | TIF back | TIF next |
|-----------|-------------|-------------|-------------|
| 00000000: | 00 00 00 00 | 00 00 00 00 | 00 00 00 4A |
| 0000004A: | 00 00 00 00 | 00 00 00 00 | 00 00 04 56 |
| 00000456: | 00 00 00 00 | 00 00 00 4A | 00 00 08 62 |
| 00000862: | 00 00 00 00 | 00 00 04 56 | 00 00 0C 6E |
| ... | | | |
| 0016E776: | 00 00 00 00 | 00 16 E5 30 | 00 16 E7 C0 |
| 0016E7C0: | 00 00 00 01 | 00 16 E7 76 | 00 16 E7 CC |
| 0016E7CC: | 00 00 00 01 | 00 16 E7 C0 | 00 16 E7 D8 |
| 0016E7D8: | EOF | | |

exception TotalDepth.LIS.core.TifMarker.ExceptionTifMarker

Specialisation of exception for Physical Records.

TotalDepth.LIS.core.TifMarker.TIF_FIRST_WORD_LIMIT = 65547

The maximum possible size of the first ‘next’ word. If larger than this then the words are written wrongly as little-endian and need to be reversed This is calculated as the maximum PR length + TIF bytes.

TotalDepth.LIS.core.TifMarker.TIF_NUM_WORDS = 3

Number of words in a TIF marker

TotalDepth.LIS.core.TifMarker.TIF_TOTAL_BYTES = 12

Number of bytes in a TIF marker

TotalDepth.LIS.core.TifMarker.TIF_WORD_ALL_FORMAT = <Struct object>

struct.Struct() format for a TIF marker

TotalDepth.LIS.core.TifMarker.TIF_WORD_ALL_FORMAT_WRONG_SEX = <Struct object>

struct.Struct() format for a TIF marker written wrongly as little-endian

TotalDepth.LIS.core.TifMarker.TIF_WORD_BYTES = 4

Number of bytes in a TIF word

```
TotalDepth.LIS.core.TifMarker.TIF_WORD_FORMAT = <Struct object>
    struct.Struct() format for a TIF word

TotalDepth.LIS.core.TifMarker.TIF_WORD_FORMAT_WRONG_SEX = <Struct object>
    struct.Struct() format for a TIF word written wrongly as little-endian

class TotalDepth.LIS.core.TifMarker.TifMarkerBase (raiseOnError=True)
    Base class for TIF markers.

    eof
        True if I have encountered a EOF marker.

    markers ()
        Current values of markers as a tuple of three integers.

    reportError (theMsg)
        Reports the error. I constructed with raiseOnError as True this will raise a ExceptionTifMarker otherwise
        it will write the error to the log.

    reset ()
        Resets the TIF markers to all zero, this means hasPrevious is False.

    strHeader ()
        Header string for an ASCII dump.

class TotalDepth.LIS.core.TifMarker.TifMarkerRead (theStream, allowPrPadding=False)
    Class for reading TIF markers. This will automatically determine if TIF markers are present and automatically
    correct ill-formed little-endian TIF markers.

    theStream - the file stream.

    allowPrPadding - If True this will consume spurious padding bytes after the Physical Record tail i.e. the TIF
    markers determine the Physical Record structure rather than the Physical Record Headers.

    hasPrevious
        True if a Physical Record has been read, cleared on reset().

    read (theStream)
        Read TIF markers from a RawStream object. Returns the stream tell() or None of the start of the TIF
        marker. This is not necessarily the same as the stream tell() seen by the caller as we might consume PR
        padding.

    reset ()
        Calling reset() means that the caller is probably randomly accessing the file so we can not error check the
        previous marker in the same way that we can if we are reading the file linearly.

class TotalDepth.LIS.core.TifMarker.TifMarkerWrite
    Class for writing TIF markers.

    close (theStream)
        Write TIF EOF markers.

    write (theStream, theLen)
        Write TIF markers to a RawStream object. theLen must be the length of the Physical Record including the
        PRH and PRT.
```

Physical Record Handler

Physical Record Attributes

| Bit | Description |
|-------|-----------------------------------------------------------|
| 15 | Unused, reserved |
| 14 | Physical record type (only 0 is defined) |
| 13-12 | 00 - No checksum, 01 - 16bit checksum, 10, 11 - Undefined |
| 11 | Unused, reserved |
| 10 | If 1 File number is present in trailer |
| 09 | If 1 Record number is present in trailer |
| 08 | Unused |
| 07 | Unused, reserved |
| 06 | If 1 then a previous parity error has occurred |
| 05 | If 1 then a previous checksum error has occurred |
| 04 | Unused |
| 03 | Unused, reserved |
| 02 | Unused |
| 01 | If 1 there is a predecessor Physical Record |
| 00 | If 1 there is a successor Physical Record |

exception `TotalDepth.LIS.core.PhysRec.ExceptionPhysRec`

Specialisation of exception for Physical Records.

exception `TotalDepth.LIS.core.PhysRec.ExceptionPhysRecEOF`

Physical Record unexpected EOF.

exception `TotalDepth.LIS.core.PhysRec.ExceptionPhysRecUndefinedChecksum`

Physical Record encountered undefined checksum bit.

exception `TotalDepth.LIS.core.PhysRec.ExceptionPhysRecUnknownType`

Encountered unknown type 1 Physical Record.

exception `TotalDepth.LIS.core.PhysRec.ExceptionPhysRecWrite`

Physical Record writing.

exception `TotalDepth.LIS.core.PhysRec.ExceptionPhysRecTail`

Physical Record Trailer exception.

`TotalDepth.LIS.core.PhysRec.PR_PRH_LEN_FORMAT = <Struct object>`

PR Header 4 bytes long, two big-endian 16 bit numbers The struct.Struct() format for the Physical Record Header

`TotalDepth.LIS.core.PhysRec.PR_PRH_ATTR_FORMAT = <Struct object>`

The struct.Struct() format for the Physical Record Header attributes

`TotalDepth.LIS.core.PhysRec.PR_PRH_LENGTH = 4`

The length of the Physical Record Header

`TotalDepth.LIS.core.PhysRec.PR_ATTRIBUTE_BITS = 16`

Number of bits in the 2 byte attributes

`TotalDepth.LIS.core.PhysRec.PR_SUCCESSOR_ATTRIBUTE_BIT = 0`

Successor bit position

`TotalDepth.LIS.core.PhysRec.PR_PREDECESSOR_ATTRIBUTE_BIT = 1`

Predessor bit position

```

TotalDepth.LIS.core.PhysRec.PR_OLD_CHECK_ERROR_BIT = 5
    Checksum error bit position

TotalDepth.LIS.core.PhysRec.PR_OLD_PARITY_ERROR_BIT = 6
    Parity error bit position

TotalDepth.LIS.core.PhysRec.PR_RECORD_NUMBER_BIT = 9
    Bit position to indicate there is a record number in the trailer

TotalDepth.LIS.core.PhysRec.PR_FILE_NUMBER_BIT = 10
    Bit position to indicate there is a file number in the trailer

TotalDepth.LIS.core.PhysRec.PR_CHECKSUM_BIT = 12
    Bit position to indicate there is a 16bit checksum in the trailer

TotalDepth.LIS.core.PhysRec.PR_CHECKSUM_UNDEFINED_BIT = 13
    Bit position to indicate checksum is undefined

TotalDepth.LIS.core.PhysRec.PR_TYPE_BIT = 14
    Bit position to indicate Physical Record Type

TotalDepth.LIS.core.PhysRec.PR_ATTRIBUTE_UNUSED_ONLY_MASK = 276
    Unused only bits - i.e. Unused but not Unused, reserved

TotalDepth.LIS.core.PhysRec.PR_ATTRIBUTE_UNUSED_RESERVED_MASK = 34952
    Unused, reserved bit mask

TotalDepth.LIS.core.PhysRec.PR_ATTRIBUTE_UNUSED_MASK = 0
    Unused and Unused, reserved bits, 0x899C

TotalDepth.LIS.core.PhysRec.PR_PRT_REC_NUM_FORMAT = <Struct object>
    The struct.Struct() format for the Physical Record Trailer record number

TotalDepth.LIS.core.PhysRec.PR_PRT_REC_NUM_LEN = 2
    The length of the Physical Record Trailer for the record number

TotalDepth.LIS.core.PhysRec.PR_PRT_REC_NUM_MIN = -32768
    The minimum record number

TotalDepth.LIS.core.PhysRec.PR_PRT_REC_NUM_MAX = 32767
    The maximum record number

TotalDepth.LIS.core.PhysRec.PR_PRT_FILE_NUM_FORMAT = <Struct object>
    The struct.Struct() format for the Physical Record Trailer file number

TotalDepth.LIS.core.PhysRec.PR_PRT_FILE_NUM_LEN = 2
    The length of the Physical Record Trailer for the file number

TotalDepth.LIS.core.PhysRec.PR_PRT_FILE_NUM_MIN = -32768
    The minimum file number

TotalDepth.LIS.core.PhysRec.PR_PRT_FILE_NUM_MAX = 32767
    The maximum file number

TotalDepth.LIS.core.PhysRec.PR_PRT_CHECKSUM_FORMAT = <Struct object>
    The struct.Struct() format for the Physical Record Trailer checksum

TotalDepth.LIS.core.PhysRec.PR_PRT_CHECKSUM_LEN = 2
    The length of the Physical Record Trailer for the checksum

TotalDepth.LIS.core.PhysRec.PR_MAX_LENGTH = 65535
    Maximum possible Physical Record length represented by an unsigned 16 bit int

```

class TotalDepth.LIS.core.PhysRec.**PhysRecBase** (*theFileId, keepGoing*)
Base class for physical record read and write. TODO: Checksum reading, writing and testing.

close ()
Close the underlying stream, further operations will raise a ValueError.

strHeader ()
Returns the header string to go at the top of a list of `__str__` ().

class TotalDepth.LIS.core.PhysRec.**PhysRecRead** (*theFile, theFileId=None, keepGoing=False*)
Specialisation of PhysRecBase for reading streams.

readLrBytes (*theSize=-1, theLd=None*)
Reads theSize logical data bytes and returns it as a bytes() object. If theSize is -1 all logical data for this logical record is returned. If theLd is not None it is extended and returned, otherwise a new bytes() object is created and returned. Returns None on end of logical record.

skipLrBytes (*theSize=-1*)
Skips logical data and returns a count of skipped bytes. If theSize is -1 all logical data for this logical record is skipped positioning the stream at end of this logical record (Note: not the beginning of the next logical record). Returns 0 on end of logical record.

skipToNextLr ()
Skips all remaining logical data, the PR trailer, and the next PR header. This positions stream at the start of the next logical record. May raise an ExceptionPhysRecEOF if there is no further Logical or Physical record. Returns the number of Logical Data bytes skipped.

tellLr ()
Returns the absolute file position of the start current Logical record. This value can be safely used in seekLr.

tell ()
Returns the absolute position of the file.

seekLr (*offset*)
External setting of file position directly to the beginning of a PRH or TIF marker (if present). The caller is fully responsible for getting this right!

seekCurrentLrStart ()
Setting the file position directly to the beginning of a PRH or TIF marker (if present) for the current Logical Record.

hasLd ()
Returns True if there is logical data to be read, False otherwise. NOTE: This will return False on file initialisation and only return True once the Physical Record Header has been read.

ldRemaingInPr ()
Returns the number of bytes remaining in this particular Physical Record. NOTE: The can be 0 and hasLd() be True if at the end of a Physical Record that has a successor record.

genLd ()
A generator that produces a tuple of (logical data, isLrStart) where: logical data - A bytes() object for the logical data in the current PR. isLrStart - A boolean that is True of that LogicalData is the start of a logical record. NOTE: This rewinds the current state of this instance.

class TotalDepth.LIS.core.PhysRec.**PhysRecTail** (*hasRecNum=False, fileNum=None, hasChecksum=False*)
Represents Physical Record Tail fields.

prhAttr
Returns the PRH attributes, to be or'd with any other attributes.

hasTail ()

Returns True if any PRT field is present, False otherwise.

computeChecksum (theB)

Computes the checksum of the byte stream.

```
class TotalDepth.LIS.core.PhysRec.PhysRecWrite (theFile,                theFileId=None,
                                                keepGoing=False,          has-
                                                Tif=False,                thePrLen=65535,
                                                thePrt=<TotalDepth.LIS.core.PhysRec.PhysRecTail
                                                object>)
```

Specialisation of PhysRecBase for writing to files.

close ()

Close the Physical Record Handler and the underlying stream.

writeLr (theLr)

Splits a Logical Record into into Physical Records and writes them to the stream. These Physical Records have trailer records if required. Returns the tell() of the start of the LR.

Logical Record Handler

Handles LIS Logical Records.

exception TotalDepth.LIS.core.LogiRec.ExceptionLr

Specialisation of exception for Logical Records.

exception TotalDepth.LIS.core.LogiRec.ExceptionLrNotImplemented

Logical Records that have no implementation here.

exception TotalDepth.LIS.core.LogiRec.ExceptionCbWrite

Raised when creating a component block with Python native types that has illogical or conflicting data.

TotalDepth.LIS.core.LogiRec.LR_TYPE_NORMAL_DATA = 0

Normal data record containing log data

TotalDepth.LIS.core.LogiRec.LR_TYPE_ALTERNATE_DATA = 1

Alternate data.

TotalDepth.LIS.core.LogiRec.LR_TYPE_JOB_ID = 32

Job identification

TotalDepth.LIS.core.LogiRec.LR_TYPE_WELL_DATA = 34

Well site data

TotalDepth.LIS.core.LogiRec.LR_TYPE_TOOL_INFO = 39

Tool string info

TotalDepth.LIS.core.LogiRec.LR_TYPE_ENCRYPTED_TABLE = 42

Encrypted table dump

TotalDepth.LIS.core.LogiRec.LR_TYPE_TABLE_DUMP = 47

Table dump

TotalDepth.LIS.core.LogiRec.LR_TYPE_DATA_FORMAT = 64

Data format specification record

TotalDepth.LIS.core.LogiRec.LR_TYPE_DATA_DESCRIPTOR = 65

Data descriptor (not defined in the LIS79 Description Reference Manual)

TotalDepth.LIS.core.LogiRec.LR_TYPE_TU10_BOOT = 95

TU10 software boot

TotalDepth.LIS.core.LogiRec.LR_TYPE_BOOTSTRAP_LOADER = 96
Bootstrap loader

TotalDepth.LIS.core.LogiRec.LR_TYPE_CP_KERNEL = 97
CP-kernel loader boot

TotalDepth.LIS.core.LogiRec.LR_TYPE_PROGRAM_FILE_HEAD = 100
Program file header

TotalDepth.LIS.core.LogiRec.LR_TYPE_PROGRAM_OVER_HEAD = 101
Program overlay header

TotalDepth.LIS.core.LogiRec.LR_TYPE_PROGRAM_OVER_LOAD = 102
Program overlay load

TotalDepth.LIS.core.LogiRec.LR_TYPE_FILE_HEAD = 128
File header

TotalDepth.LIS.core.LogiRec.LR_TYPE_FILE_TAIL = 129
File trailer

TotalDepth.LIS.core.LogiRec.LR_TYPE_TAPE_HEAD = 130
Tape header

TotalDepth.LIS.core.LogiRec.LR_TYPE_TAPE_TAIL = 131
Tape trailer

TotalDepth.LIS.core.LogiRec.LR_TYPE_REEL_HEAD = 132
Reel header

TotalDepth.LIS.core.LogiRec.LR_TYPE_REEL_TAIL = 133
Reel trailer

TotalDepth.LIS.core.LogiRec.LR_TYPE_EOF = 137
Logical EOF (end of file)

TotalDepth.LIS.core.LogiRec.LR_TYPE_BOT = 138
Logical BOT (beginning of tape)

TotalDepth.LIS.core.LogiRec.LR_TYPE_EOT = 139
Logical EOT (end of tape)

TotalDepth.LIS.core.LogiRec.LR_TYPE_EOM = 141
Logical EOM (end of medium)

TotalDepth.LIS.core.LogiRec.LR_TYPE_OPERATOR_INPUT = 224
Operator command inputs

TotalDepth.LIS.core.LogiRec.LR_TYPE_OPERATOR_RESPONSE = 225
Operator response inputs

TotalDepth.LIS.core.LogiRec.LR_TYPE_SYSTEM_OUTPUT = 227
System outputs to operator

TotalDepth.LIS.core.LogiRec.LR_TYPE_FLIC_COMMENT = 232
FLIC comment

TotalDepth.LIS.core.LogiRec.LR_TYPE_BLANK_RECORD = 234
Blank record/CSU comment

TotalDepth.LIS.core.LogiRec.LR_TYPE_PICTURE = 85
Picture

init (*theLen*)
Returns a string of spaces of the supplied length.

__str__ ()
String representation.

desc
Description of the LR type.

__weakref__
list of weak references to the object (if defined)

class TotalDepth.LIS.core.LogiRec.**LrMarker** (*theType, theAttr*)
A marker record such as EOF BOT EOT EOM.

class TotalDepth.LIS.core.LogiRec.**LrEOF** (*attr=0*)
A EOF marker record.

class TotalDepth.LIS.core.LogiRec.**LrEOFRead** (*theFile*)
A EOF marker record read from a file.

class TotalDepth.LIS.core.LogiRec.**LrBOT** (*attr=0*)
A BOT marker record.

class TotalDepth.LIS.core.LogiRec.**LrBOTRead** (*theFile*)
A BOT marker record read from a file.

class TotalDepth.LIS.core.LogiRec.**LrEOT** (*attr=0*)
A EOT marker record.

class TotalDepth.LIS.core.LogiRec.**LrEOTRead** (*theFile*)
A EOT marker record read from a file.

class TotalDepth.LIS.core.LogiRec.**LrEOM** (*attr=0*)
A EOM marker record.

class TotalDepth.LIS.core.LogiRec.**LrEOMRead** (*theFile*)
A EOM marker record read from a file.

class TotalDepth.LIS.core.LogiRec.**LrWithDateField** (*theType, theAttr*)
ABC for classes that have the YY/MM/DD date field.

ymd
Returns the YY/MM/DD date field to a year, month, day tuple or None.

class TotalDepth.LIS.core.LogiRec.**LrFileHeadTail** (*theType, theAttr*)
Parent class of FileHead, FileTail that have identical structure.

read (*theFile*)
Read from a LIS physical file.

contFileName
Continuation file name.

class TotalDepth.LIS.core.LogiRec.**LrFileHead** (*theType, theAttr*)
Specific class of File Head.

prevFileName
Previous file name.

class TotalDepth.LIS.core.LogiRec.**LrFileHeadRead** (*theFile*)
Specific class of File head read from a file.

```

class TotalDepth.LIS.core.LogiRec.LrFileTail (theType, theAttr)
    Specific class of File Tail.

    nextFileName
        Next file name.

class TotalDepth.LIS.core.LogiRec.LrFileTailRead (theFile)
    Specific class of File tail read from a file.

class TotalDepth.LIS.core.LogiRec.LrReelTapeHeadTail (theType, theAttr)
    Parent class of Reel/Tape Head/Tail that have identical structure.

class TotalDepth.LIS.core.LogiRec.LrTapeHeadTail (theType, theAttr)
    Tape head or tail Logical Record.

class TotalDepth.LIS.core.LogiRec.LrTapeHead (theType, theAttr)
    Tape head Logical Record.

    prevTapeName
        Previous tape name.

class TotalDepth.LIS.core.LogiRec.LrTapeHeadRead (theFile)
    Specific class of Tape head read from a file.

class TotalDepth.LIS.core.LogiRec.LrTapeTail (theType, theAttr)
    Tape tail Logical Record.

    nextTapeName
        Next tape name.

class TotalDepth.LIS.core.LogiRec.LrTapeTailRead (theFile)
    Specific class of Tape tail read from a file.

class TotalDepth.LIS.core.LogiRec.LrReelHeadTail (theType, theAttr)
    Reel head or tail Logical Record.

class TotalDepth.LIS.core.LogiRec.LrReelHead (theType, theAttr)
    Reel head Logical Record.

    prevReelName
        Previous reel name.

class TotalDepth.LIS.core.LogiRec.LrReelHeadRead (theFile)
    Specific class of Reel head read from a file.

class TotalDepth.LIS.core.LogiRec.LrReelTail (theType, theAttr)
    Reel tail Logical Record.

    nextReelName
        Next reel name.

class TotalDepth.LIS.core.LogiRec.LrReelTailRead (theFile)
    Specific class of Reel tail read from a file.

class TotalDepth.LIS.core.LogiRec.LrMisc (theType, theAttr)
    Miscellaneous Logical Record.

class TotalDepth.LIS.core.LogiRec.LrMiscRead (theFile)
    Miscellaneous Logical Record read from a LIS file.

TotalDepth.LIS.core.LogiRec.COMPONENT_BLOCK_TABLE = 73
    Type of first Component Blocks in the table

```

`TotalDepth.LIS.core.LogiRec.COMPONENT_BLOCK_DATUM_BLOCK_START = 0`
Type of first Component Blocks in the Datum Block i.e. row

`TotalDepth.LIS.core.LogiRec.COMPONENT_BLOCK_DATUM_BLOCK_ENTRY = 69`
Component Block type that describes an entry in a Datum Block i.e. a cell

exception `TotalDepth.LIS.core.LogiRec.ExceptionLrTable`
Specialisation of exception for Table Logical Records.

exception `TotalDepth.LIS.core.LogiRec.ExceptionLrTableInit`
Table `__init__()` issues.

exception `TotalDepth.LIS.core.LogiRec.ExceptionLrTableInternalStructuresCorrupt`
Raised when there are inconsistencies with the IR of the table.

exception `TotalDepth.LIS.core.LogiRec.ExceptionLrTableCompose`
Table creation (not from file) issues.

exception `TotalDepth.LIS.core.LogiRec.ExceptionLrTableRow`
TableRow issues.

exception `TotalDepth.LIS.core.LogiRec.ExceptionLrTableRowInit`
TableRow `__init__()` issues.

exception `TotalDepth.LIS.core.LogiRec.ExceptionCbEngValInit`
CbEngVal.`__init__()` issues such as unknown rep code.

class `TotalDepth.LIS.core.LogiRec.CbEngVal`
Contains the data from a Component Block and has an EngVal

CB_TYPES = (73, 0, 69)
Allowable Component Block types

setValue (*v*)
Sets the value to *v*.

lisBytes ()
Return a bytes() array from the internal representation.

value
The value of the Component Block or None.

status
Returns True if the value is b'ALLO', False otherwise.

__weakref__
list of weak references to the object (if defined)

class `TotalDepth.LIS.core.LogiRec.CbEngValRead` (*theFile*)
Contains the data from a Component Block and has an EngVal read from a file.

__init__ (*theFile*)
Initialise. This will raise a `TypeError` if *theFile*.`unpack` returns `None` i.e. when not enough data to create a Component Block.

class `TotalDepth.LIS.core.LogiRec.CbEngValWrite` (*t, v, m, **kwargs*)
A Component Block and has an EngVal created directly.

__init__ (*t, v, m, **kwargs*)
Initialise component block with type, value, mnemonic and optional key words.

class `TotalDepth.LIS.core.LogiRec.TableRow` (*theCb*)
Represents a row of a table and consists of CbEngVal objects.

genCells ()
yields each CbEngVal.

__len__ ()
The number of cells in the row.

value
The name of the row i.e. the value of block 0.

addCb (*theCb*)
Adds a component block onto the end of the row. Returns the mnemonic field from the component block.

__getitem__ (*key*)
If key is an integer or slice this returns a CbEngVal by index(es). If key is a bytes() object then this returns a CbEngVal by label. May raise a KeyError or IndexError.

__contains__ (*key*)
Returns True if this row has a column named key.

__weakref__
list of weak references to the object (if defined)

class TotalDepth.LIS.core.LogiRec.**LrTable** (*theType, theAttr*)
Table-like Logical Record.

__init__ (*theType, theAttr*)
Base class constructor. theType, theAttr are byte objects i.e. integers 0 to 255

genRows ()
yields each TableRow. TODO: parameter to sort or reverse.

genRowNames (*sort=0*)
yields each TableRow name. If sort > 0 then the results are sorted. If sort < 0 the results are reverse sorted

retRowByMnem (*m*)
Returns the TableRow from a Mnem.Mnem object. i.e. the table row that has a b'MNEM' column whose value matches m. May raise a KeyError. Note: an IndexError would mean that self.__mnemRowIndex is corrupt.

isSingleParam
True if this table is a list of single parameters (i.e. type 0 blocks).

value
The name of the table or None i.e. the value of the first block.

__getitem__ (*key*)
If key is an integer or slice this returns block by index(es). If key is a bytes() object then this returns row by label. May raise a KeyError or IndexError.

__contains__ (*key*)
Returns True if this row has a row named key.

__len__ ()
Number of rows in the table.

rowLabels ()
Returns dictionary view of row values (unordered).

rowMnems ()
Returns dictionary view of row Mnem.Mnem objects (unordered).

colLabels ()
Returns ordered super-set of column values. Not all rows have these.

startNewRow (*theCbEv*)

Starts a new row from the component block. Returns theCbEv.mnem value.

addDatumBlock (*theCbEv*)

Adds a component block to the last row. Returns theCbEv value.

genRowValuesInColOrder (*theRow*)

Yields table cells in a particular row in column order.

genLisBytes ()

Yields chunks of binary LIS data (actually each component block).

class TotalDepth.LIS.core.LogiRec.**LrTableRead** (*theFile*)

A table-like Logical Record read from a LIS file.

class TotalDepth.LIS.core.LogiRec.**LrTableWrite** (*theType, theName, theMnemS, theTable*)

Creates a table from internal Python data structures.

theType is the table type e.g. b'FILM'

theMnemS is the list of column names, theTable members must fit this size.

If an element of the table is a tuple or a list it is assumed to be (value, units).

__init__ (*theType, theName, theMnemS, theTable*)

Construct a table from internal data that must be bytes/float/int. theType is the table type e.g. b'FILM' theMnemS is the list of column names, theTable members must fit this size. If an element of the table is a tuple or a list it is assumed to be (value, units).

exception TotalDepth.LIS.core.LogiRec.**ExceptionEntryBlock**

Specialisation of exception for Entry Blocks.

exception TotalDepth.LIS.core.LogiRec.**ExceptionEntryBlockSetInit**

Exception for EntryBlockSet.__init__().

class TotalDepth.LIS.core.LogiRec.**EntryBlockRead**

An entry block read from a LIS file.

class TotalDepth.LIS.core.LogiRec.**EntryBlockSet**

Represents the set of Entry Blocks in a DFSR.

ATTR_MAP = {'dataType': 1, 'dsbType': 2, 'upDown': 4, 'optLogScale': 5, 'frameSpace': 6}

Map of supported attributes i.e. those that are 'interesting'

EB_DOC = {0: 'Terminator, size is chosen to make total size even.', 1: 'Data Record '}

Documentation about each Entry Block

BLOCKS_TO_SKIP = (10,)

List of block numbers that are not written out, also _setLisSizeEven() and lisSize() ignore these.

__getattr__ (*name*)

Returns the Entry Block corresponding to the name.

__getitem__ (*key*)

This returns an Entry block by integer index.

logUp

True if the logging direction is up (X decreasing). Note: not logUp and not logDown is possible to be True e.g. time log.

logDown

True if the logging direction is down (X increasing). Note: not logUp and not logDown is possible to be True e.g. time log.

xInc

True if the logging X increases (down or time log).

opticalLogScale

Returns the Units corresponding to Entry Block 5: 'Optical Log Scale' This will be a LENG or TIME unit or empty if undefined.

lisSize()

Returns the totla size of the Entry Block set.

setEntryBlock(*theEb*)

Sets an Entry Block.

readFromFile(*theFile*)

Reads from a File object. NOTE: *theFile*.hasLd() must be True so the Logical Record Header must have been read already.

lisBytes()

Returns the Entry Block set as an array of bytes.

lisByteList()

Returns a list of bytes() objects, one for each entry block.

__weakref__

list of weak references to the object (if defined)

exception TotalDepth.LIS.core.LogiRec.ExceptionDatumSpecBlock

Specialisation of exception for Datum Specification Blocks.

class TotalDepth.LIS.core.LogiRec.DatumSpecBlock

This represents as Datum Specification Block.

isNull

True if this block is compromised in any way and should be ignored when composing a DFSR. The critical test is whether the data from this channel will be in the frame.

samples(*theSc*)

Returns the number of samples in a sub-channel.

bursts(*theSc*)

Returns the (samples, burst) for a sub-channel (bursts are invariant over sub-channels).

values()

Returns the total number of discrete values per frame for a single channel.

subChMnem(*theSc*)

Returns the curve Mnemonic for a particular sub-channel or None if unknown.

__weakref__

list of weak references to the object (if defined)

class TotalDepth.LIS.core.LogiRec.DatumSpecBlockRead(*theF*)

This represents as Datum Specification Block read from a file.

class TotalDepth.LIS.core.LogiRec.LrDFSR(*theType, theAttr*)

Data Format Specification Record.

class TotalDepth.LIS.core.LogiRec.LrDFSRRRead(*theFile*)

Data Format Specification Record read from a file.

class TotalDepth.LIS.core.LogiRec.LrNormalAlternateData(*theType, theAttr*)

Class for Normal and Alternate data i.e. curve data.

class TotalDepth.LIS.core.LogiRec.**LrNormalAlternateDataRead** (*theFile*)

Class for Normal and Alternate data i.e. curve data.

class TotalDepth.LIS.core.LogiRec.**LrFactory**

Provides a despatch mechanism for generating Logical Records. This can be sub-classed to create different sets of Logical Records. For example the Indexer creates minimal logical records.

__weakref__

list of weak references to the object (if defined)

class TotalDepth.LIS.core.LogiRec.**LrFactoryRead**

A factory for generating complete Logical Records from a file.

retLrFromFile (*theFile*)

Given a LIS file this reads one Logical Record, and returns the appropriate Logical Record object or None.

FileIndexer

#Contents: Indexes LIS files.

Created on 10 Feb 2011

@author: p2ross

exception TotalDepth.LIS.core.FileIndexer.**ExceptionFileIndex**

Specialisation of exception for the LIS file indexer.

class TotalDepth.LIS.core.FileIndexer.**FileIndex** (*theF*, *xAxisIndex=0*)

Create an index for the LIS file, theF is a LIS File object.

xAxisIndex is the channel index that is regarded as the X axis (default 0). This is currently ignored in the absence of a reasonable use case.

genAll ()

Generates each index object (child class of IndexObjBase).

genLogPasses ()

Yields all IndexLogPass objects in the index.

genPlotRecords (*fromInternalRecords=True*)

This provides the minimal information for creating a Plot. It yields a PlotRecordSet that has (tell_FILM, tell_PRES, tell_AREA, tell_PIP, IndexLogPass) objects that are not separated by delimiter records. tell_FILM is the file offset of the FILM record. tell_PRES is the file offset of the PRES record. tell_AREA is None or the file offset of the AREA record. tell_PIP is None or the file offset of the PIP record. IndexLogPass is a IndexLogPass object.

jsonObject ()

Return an Python object that can be JSON encoded.

longDesc ()

Returns a string that is the long description of this object.

lrTypes

Returns a list of Logical Record types (integers) that is in the index.

numLogPasses ()

Returns the number of IndexLogPass objects in the index.

class TotalDepth.LIS.core.FileIndexer.**IndexFileHead** (*tell*, *lrType*, *theF*)

Indexes a File header. The full Logical record is retained.

class TotalDepth.LIS.core.FileIndexer.**IndexFileHeadTail** (*tell, lrType, theF, theClass*)

Indexes a File header or trailer. The full Logical record is retained.

tocStr ()

Returns a ‘pretty’ string suitable for a table of contents.

class TotalDepth.LIS.core.FileIndexer.**IndexFileTail** (*tell, lrType, theF*)

Indexes a File trailer. The full Logical record is retained.

class TotalDepth.LIS.core.FileIndexer.**IndexLogPass** (*tell, lrType, theF, xAxisIndex=0*)

The index of a Log Pass. This contains a LogPass object.

xAxisIndex is the channel index that is regarded as the X axis. This is the indirect axis if present or defaults to channel 0.

add (*tell, lrType, theF*)

Add an IFLR.

canAdd (*iflrType*)

Returns the IFLR type that this EFLR can describe.

iflrType ()

Returns the IFLR type that this EFLR can describe.

jsonObject ()

Return an Python object that can be JSON encoded.

logPass

The LogPass object.

tocStr ()

Returns a ‘pretty’ string suitable for a table of contents.

class TotalDepth.LIS.core.FileIndexer.**IndexLrFull** (*tell, lrType, theF, theClass*)

Takes a full LR and assigns it to self._lr.

theClass is a cls that is use to instantiate a Logical Record object at the current file position.

setLogicalRecord (*theFile*)

Sets the logicalRecord property to an LogiRec object from theFile.

class TotalDepth.LIS.core.FileIndexer.**IndexNone** (*tell, lrType, theF*)

NULL class just takes the LR information and skips to next LR.

class TotalDepth.LIS.core.FileIndexer.**IndexObjBase** (*tell, lrType, theF*)

Base class for indexed objects.

tell - The file position of the Logical Record as an integer.

lrType - The Logical Record type as an integer.

theF - The LIS File object. The file ID is recorded for later error checking.

canAdd (*iflrType*)

Returns True if this can accumulate another IFLR.

iflrType ()

Returns the IFLR type that this EFLR can describe.

isDelimiter

True if this represents a delimiter record e.g. File Head/Tail.

jsonObject ()

Return an Python object that can be JSON encoded.

logicalRecord

The underlying LogiRec object or None.

lrType

The Logical Record type, in integer.

setLogicalRecord (*theFile*)

Sets the logicalRecord property to an LogiRec object from theFile.

tell

The file offset of the Logical Record.

tocStr ()

Returns a ‘pretty’ string suitable for a table of contents.

class TotalDepth.LIS.core.FileIndexer.**IndexReelHead** (*tell, lrType, theF*)

Indexes a Reel header. The full Logical record is retained.

class TotalDepth.LIS.core.FileIndexer.**IndexReelHeadTail** (*tell, lrType, theF, the-
Class*)

Indexes a Reel header or trailer. The full Logical record is retained.

tocStr ()

Returns a ‘pretty’ string suitable for a table of contents.

class TotalDepth.LIS.core.FileIndexer.**IndexReelTail** (*tell, lrType, theF*)

Indexes a Reel trailer. The full Logical record is retained.

class TotalDepth.LIS.core.FileIndexer.**IndexTable** (*tell, lrType, theF*)

Table type logical records. Here we capture the first component block so that we know the name of the table.

jsonObject ()

Return an Python object that can be JSON encoded.

name

The name of the table from the first component block.

setLogicalRecord (*theFile*)

Sets the logicalRecord property to an LogiRec.LrTable() object.

tocStr ()

Returns a ‘pretty’ string suitable for a table of contents.

class TotalDepth.LIS.core.FileIndexer.**IndexTapeHead** (*tell, lrType, theF*)

Indexes a Tape header. The full Logical record is retained.

class TotalDepth.LIS.core.FileIndexer.**IndexTapeHeadTail** (*tell, lrType, theF, the-
Class*)

Indexes a Tape header or trailer. The full Logical record is retained.

tocStr ()

Returns a ‘pretty’ string suitable for a table of contents.

class TotalDepth.LIS.core.FileIndexer.**IndexTapeTail** (*tell, lrType, theF*)

Indexes a Tape trailer. The full Logical record is retained.

class TotalDepth.LIS.core.FileIndexer.**IndexUnknownInternalFormat** (*tell, lrType,
theF*)

Binary verbatim class for things like encrypted records, images, raw table dumps and so on.

setLogicalRecord (*theFile*)

Sets the logicalRecord property to an LogiRec.LrTable() object.

class TotalDepth.LIS.core.FileIndexer.**PlotRecordSet**

A POD class that can contain a set of references to the essential (plus optional) logical records for plotting.

canPlotFromExternalRecords ()

True if I have a valid value that could be yielded, i.e. the minimum information from the file that allows a plot using some external definition of what has to be plotted. In practice this means a LogPass.

canPlotFromInternalRecords ()

True if I have a valid value that could be yielded, i.e. the minimum information from the file that allows a plot. In practice this means a FILM, PRES record and a LogPass.

Usage

Examples

Using a LIS Indexer

Source:

```
myFilePath = "Spam/Eggs.LIS"
# Open a LIS file
myFi = File.FileRead(myFilePath, theFileId=myFilePath, keepGoing=True)
# Index the LIS file
myIdx = FileIndexer.FileIndex(myFi)
# Ask the index for all the LogPass objects, these do not have the frameSet populated
→yet
for aLr in myIdx.genAll():
    print(aLr)
```

Typical result:

```
tell: 0x00000000 type=128 <TotalDepth.LIS.core.FileIndexer.IndexFileHead object at
→0x10197ff90>
tell: 0x00000050 type= 34 name=b'TOOL' <TotalDepth.LIS.core.FileIndexer.IndexTable
→object at 0x10197ffd0>
tell: 0x000001ea type= 34 name=b'INPU' <TotalDepth.LIS.core.FileIndexer.IndexTable
→object at 0x10197fd10>
tell: 0x00002342 type= 34 name=b'OUTP' <TotalDepth.LIS.core.FileIndexer.IndexTable
→object at 0x101b0b1d0>
tell: 0x00003622 type= 34 name=b'CONS' <TotalDepth.LIS.core.FileIndexer.IndexTable
→object at 0x101b0bed0>
tell: 0x0000456a type= 34 name=b'CONS' <TotalDepth.LIS.core.FileIndexer.IndexTable
→object at 0x101b0b590>
tell: 0x000064aa type= 34 name=b'PRES' <TotalDepth.LIS.core.FileIndexer.IndexTable
→object at 0x101b0b050>
tell: 0x00006efe type= 34 name=b'FILM' <TotalDepth.LIS.core.FileIndexer.IndexTable
→object at 0x101b0bfd0>
tell: 0x00006fc6 type= 34 name=b'AREA' <TotalDepth.LIS.core.FileIndexer.IndexTable
→object at 0x101b0bb50>
<TotalDepth.LIS.core.LogPass.LogPass object at 0x101b06490>
<TotalDepth.LIS.core.LogPass.LogPass object at 0x101b12410>
tell: 0x0017cbee type=129 <TotalDepth.LIS.core.FileIndexer.IndexFileTail object at
→0x101b173d0>
```

Testing

The unit tests are in test/TestFileIndexer.Py

The LIS Log Pass

This describes the LIS LogPass class that encapsulates a Log Pass. A log pass is the binary log data plus the record (DFSR) that describes the format of the binary data. Internally the binary data is converted to a FrameSet that wraps a numpy array.

The LogPass module is located in `src/TotalDepth/LIS/core` and can be imported thus:

```
from TotalDepth.LIS.core import LogPass
```

LogPass API Reference

The LogPass module contains a single class LogPass that is fundamental to the way that TotalDepth handles LIS binary data.

A Log Pass is defined as a single continuous recording of log data. “Main Log”, “Repeat Section” are separate examples of Log Pass(es).

`TotalDepth.LIS.core.LogPass.EVENT_EXTRAPOLATE = 'extrapolate'`

Event to extrapolate X axis

`TotalDepth.LIS.core.LogPass.EVENT_READ = 'read'`

Event to read bytes from frame

`TotalDepth.LIS.core.LogPass.EVENT_SEEK_LR = 'seekLr'`

Event to seek to the start of a new Logical Record

`TotalDepth.LIS.core.LogPass.EVENT_SKIP = 'skip'`

Event to skip bytes in frame

exception `TotalDepth.LIS.core.LogPass.ExceptionLogPass`

Specialisation of exception for LogPass.

exception `TotalDepth.LIS.core.LogPass.ExceptionLogPassCtor`

Specialisation of exception for LogPass `__init__()`.

exception `TotalDepth.LIS.core.LogPass.ExceptionLogPassKeyError`

Raised when and internal KeyError is raised in a FrameSet access.

exception `TotalDepth.LIS.core.LogPass.ExceptionLogPassNoFrameSet`

Raised when FrameSet access is required but there has been no call to `setFrameSet()`.

exception `TotalDepth.LIS.core.LogPass.ExceptionLogPassNoType01Data`

Raised on access when there is no frame data loaded by `addType01Data()`.

class `TotalDepth.LIS.core.LogPass.LogPass` (*theDfsr, theFileId, xAxisIndex=0*)

Contains the information about a log pass which is defined as a LIS Data Format Specification Record (DFSR) plus any number of Type 0/1 Logical Records.

A LogPass must be created with a LIS DFSR and a LIS file ID. It can be then informed with `addType01Data()` which records the file positions of Type 0/1 records. When required the actual frame data can be populated with `setFrameSet()`.

theDfsr - The DFSR.

theFileId - The ID of the file, this will be checked against any File object passed to me.

xAxisIndex - The index of the DSB block that describes the X axis, if indirect X this is ignored.

addType01Data (*tellLr, lrType, lrLen, xAxisVal*)

Add an Type 0/1 logical record entry.

tellLr - the Logical Record start position in the file.

lrType - the type of the IFLR. Will raise an ExceptionLogPass if this does not match the DFSR.

lrLen - the length of the Logical record, not including the LRH.

xAxisVal - the value of the X Axis of the first frame of the Logical Record.

curveUnits (*chMnem*)

Given a curve as a Mnem.Mnem() this returns the units as a bytes object.

curveUnitsAsStr (*chMnem*)

Given a curve as a Mnem.Mnem() this returns the units as a string.

dfsr

The DFSR used for construction.

frameFromX (*theEv*)

Returns the estimated frame number from the X axis, and EngValue.

frameSet

The Frame Set as a FrameSet.FrameSet() object or None if not initialised.

frameSetLongStr ()

Returns a long (multiline) descriptive string of the Frame Set or N/A if not initialised.

genFrameSetHeadings ()

This generates a name and units for each value in a frame in the current frame set. It is useful for heading up a frame dump.

genFrameSetScNameUnit (*toAscii=True*)

This generates a name and units for sub-channel in a frame in the current frame set. It is useful for heading up a accumulate() dump.

genOutpPoints (*theMnem*)

Wrapper around the frameset generator, in fact this returns exactly that generator.

hasOutpMnem (*theMnem*)

Returns True is theMnem is in this LogPass (i.e. is in the DFSR).

iflrType

Returns the IFLR type that this LogPass describes.

isIndirectX

True if indirect X axis, False if explicit X axis channel.

jsonObject ()

Return an Python object that can be JSON encoded.

longStr ()

Returns a long (multiline) descriptive string.

nullValue

The NULL or absent value as specified in the DFSR.

numBytes

The number of bytes in the underlying frame set (i.e. LIS) representation for the curve data. Returns None if the frame set is not initialised.

outpMnemS ()

Returns all of the OUTP Mnems in this LogPass (i.e. is in the DFSR).

retExtChIndexList (*theMnemS*)

Returns a sorted, unique list of external channel indexes for a list of mnemonics. May raise a Exception-LogPassKeyError.

rle

The Logical Record Run Length Encoding as a Rle.RLEType01() object.

setFrameSet (*theFile, theFrSl=None, theChList=None*)

Populates the frames set.

theFile - The File object. Will raise an ExceptionLogPass is the file ID does not match that in the constructor.

theFrSl - A slice object that describes when LogPass frames are to be used (default all). Will raise an ExceptionLogPass is there are no frames to load i.e. addType01Data() has not been called.

theChList - A list of external channel indexes (i.e. DSB block indexes) to populate the frame set with (default all).

setFrameSetChX (*theFi, theChS, Xstart, Xstop, frStep=1*)

Loads a FramesSet using 'external' values from a File object. *theChS* is a list of channel mnemonics or None for all channels. *Xstart, Xstop* are EngVal of the start stop. *frStep* is not number of frames to step over, default means all frames.

totalFrames

The total number of frames.

type01Plan

The Frame plan, a Type01Plan.FrameSetPlan() object.

xAxisFirstEngVal

The EngVal (value, units) of the X axis of the first frame.

xAxisFirstVal

The numerical value of the X axis of the first frame.

xAxisFirstValOptical

The numerical value of the X axis of the first frame in 'optical' units.

xAxisIndex

The channel index that corresponds to the X axis.

xAxisLastEngVal

The EngVal (value, units) of the X axis of the first frame.

xAxisLastVal

The numerical value of the X axis of the last frame.

xAxisLastValOptical

The numerical value of the X axis of the last frame in 'optical' units.

xAxisSpacing

The numerical value of the X axis frame spacing. This is is the extreme range of X axis values divided by the number of frames - 1. This is +ve if the Xaxis increases, -ve if it decreases.

xAxisSpacingOptical

The numerical value of the X axis frame spacing. This is is the extreme range of X axis values divided by the number of frames - 1.

xAxisUnits

The units of the X axis.

xAxisUnitsOptical

Returns the actual units to 'optical' i.e. user friendly units. For example if the Xaxis was in b'.1IN' the 'optical' units would be b'FEET'.

LogPass Usage

Typically a LogPass will be created directly or via a LIS FileIndexer. The latter technique is recommended as it is simpler.

Direct usage

LogPass objects are used via a three step process and this reflects the sequential process of reading a LIS file:

1. Construction with a DFSR object (once).
2. Updating with the location of the binary data records that contain the frame data (once per IFLR).
3. Populating the FrameSet with real values from the file (many times).

Construction with a DFSR

A LogPass object needs to be constructed with an instance of a LogiRec.LrDFSRRRead. The LogPass will take a reference to the DFSR so the caller need not. The caller can always access the DFSR with the `.dfsr` property.

Assuming myF is a LIS File object positioned at the start of the DFSR:

```
myLp = LogPass.LogPass(LogiRec.LrDFSRRRead(myF), 'FileID')
```

Resources

At this stage no FrameSet is created so the resource usage is minimal.

Add Binary Data Records

The method `addType01Data(tellLr, lrType, lrLen, xAxisVal)` adds the position of an IFLR that contain frame data. This method takes these arguments:

| Argument | Description |
|-----------------------|------------------------------------------------------------------------------------------------------------|
| <code>tellLr</code> | The Logical Record start position (as a <code>size_t</code>) in the file. |
| <code>lrType</code> | The type of the IFLR [0 1]. Will raise an <code>ExceptionLogPass</code> if this does not match the DFSR. |
| <code>lrLen</code> | The length of the Logical Record in bytes, not including the LRH. |
| <code>xAxisVal</code> | The value of the X Axis as a number of the first frame of the Logical Record. |

This call should be made for each relevant IFLR as they are encountered in sequence.

Resources

At this stage no FrameSet is created and the arguments are encoded into an RLE object so the resource usage is minimal.

Populating the FrameSet

Once the preceding stages have been done the LogPass can be populated any number of times from the LIS file.

The method `setFrameSet(theFile, theFrSl=None, theChList=None)` constructs a new frame set with the appropriate values.

| Argument | Description |
|------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| the-File | The File object. Will raise an <code>ExceptionLogPass</code> is the file ID does not match that used in the constructor. |
| the-FrSl | A slice object that describes when LogPass frames are to be used (default all). Will raise an <code>ExceptionLogPass</code> if there are no frames to load i.e. <code>addType01Data()</code> has not been called. |
| theCh-List | A list of external channel indexes (i.e. DSB block indexes) to populate the frame set with (default all). |

Examples

Setting a frame set for all frames and all channels:

```
myLogPass.setFrameSet(myFile)
# The above line is equivalent to:
myLogPass.setFrameSet(myFile, theFrSl=None, theChList=None)
```

Setting a frame set for frames [0:16:4] i.e. frame indexes (0,4,8,12) and channels [0, 4, 7]

```
myLogPass.setFrameSet(myFile, theFrSl=slice(0,16,4), theChList=[0, 4, 7])
```

Resources

Any previous FrameSet will be freed and a new FrameSet of the appropriate dimension is created so the resource usage can be significant.

Using a LIS Indexer

A *FileIndexer* [`TotalDepth.LIS.core.FileIndexer.FileIndex`] object will perform the necessary construction of a LogPass and the population with Logical Record positions with `addType01Data()` leaving the user just to call `setFrameSet()`. Thus a `FileIndex` object imposes low resource usage until the user wishes to populate the frame set.

An indexer will index a LIS file that has multiple Log Passes (e.g. repeat section, main log etc.) so the indexer provides an iteration method for Log Passes:

```
myFilePath = "Spam/Eggs.LIS"
# Open a LIS file, keepGoing for luck!
myFi = File.FileRead(myFilePath, theFileId=myFilePath, keepGoing=True)
# Index the LIS file
myIdx = FileIndexer.FileIndex(myFi)
# Ask the index for all the LogPass objects, these do not have the frameSet populated
↪ yet
for aLp in myIdx.genLogPasses():
    # Load the FrameSet, all channels [None], all frames [None]
```

```

alp.logPass.setFrameSet(myFi, None, None)
# The FrameSet is fully populated here...
# Do something with it...

```

Testing

The unit tests are in `test/TestLogPass.py`. This should take under a second to execute.

Running the tests under coverage:

```

$ coverage run test/TestLogPass.py
TestClass.py script version "0.8.0", dated 10 Jan 2011
Author: Paul Ross
Copyright (c) Paul Ross

testSetUpTearDown (__main__.TestLogPass_LowLevel)
TestLogPass_LowLevel: Tests setUp() and tearDown(). ... ok
test_00 (__main__.TestLogPass_LowLevel)
TestLogPass_LowLevel.test_00(): Construction. ... ok
test_01 (__main__.TestLogPass_LowLevel)
TestLogPass_LowLevel.test_01(): _sliceFromList(). ... ok
test_02 (__main__.TestLogPass_LowLevel)
TestLogPass_LowLevel.test_02(): exercise various properties. ... ok
test_10 (__main__.TestLogPass_LowLevel)
TestLogPass_LowLevel.test_10(): nullValue(). ... ok

8<----- snip ----->8

test_00 (__main__.TestLogPass_UpIndirect)
TestLogPass_UpIndirect.test_00(): 3 LR, 5 fr, 4 ch. setFrameSet() All. ... ok
test_01 (__main__.TestLogPass_UpIndirect)
TestLogPass_UpIndirect.test_01(): 3 LR, 5 fr, 4 ch. setFrameSet() theFrSl=slice(0,16,
↪2). ... ok
test_02 (__main__.TestLogPass_UpIndirect)
TestLogPass_UpIndirect.test_02(): 3 LR, 5 fr, 4 ch. setFrameSet() theFrSl=slice(2,4,
↪2). ... ok
test_03 (__main__.TestLogPass_UpIndirect)
TestLogPass_UpIndirect.test_03(): 3 LR, 5 fr, 4 ch. setFrameSet() theFrSl=slice(1,5,
↪2). ... ok
test_10 (__main__.TestLogPass_UpIndirect)
TestLogPass_UpIndirect.test_10(): genFrameSetHeadings() ... ok

-----
Ran 54 tests in 0.507s

OK
CPU time =    0.510 (S)
Bye, bye!

$ coverage report -m
Name      Stmts    Miss  Cover   Missing
-----
↪-----

8<----- snip ----->8

LogPass      273      27    90%   142, 167, 182, 187, 203, 216-218, 232, 258, 273-275, ↪
↪319, 324, 412, 416, 457-459, 513, 527, 541, 557, 572, 646-647

```

| |
|--------------------------------------|
| 8<----- snip ----->8 |
| ----- |
| ↪----- |
| TOTAL 4586 1783 61% |

The LIS Frame Set

This describes the LIS FrameSet that contains the binary frame data. It is effectively a wrapper around a 2-D numpy array with specific APIs to interface that with a channel specific shape. Importantly FrameSets can be partial in that they need not hold all the data for every frame and every channel. Instead they can hold data for the frames and channels specified by the caller.

The FrameSet module is located in `src/TotalDepth/LIS/core` and can be imported thus:

```
from TotalDepth.LIS.core import FrameSet
```

FrameSet Internals

The internal representation of the FrameSet uses only Python and numpy structures and types, it is thus ignorant of the LIS file format or data structures apart from that described below.

LIS Dependancies

In the current version of the code there are a number of dependencies on knowledge of the LIS file format (or at least TotalDepth's representation of that format):

- ChArTe objects are constructed from LIS Datum Specification Block objects.
- XAxisDecl consists of a straight copy of various Entry Block values.
- XAxisDecl relies on the LIS value of the up/down flag.
- FrameSet is constructed with a DFSR and extracts the absent value form the DFSR as well as constructing ChArTe and XAxisDecl objects.
- **FrameSet has quite a lot of dependencies of Representation codes these are mainly used in two ways.**
 - Interpreting Dipmeter sub-channels.
 - `setFrameBytes()` uses the RepCode module directly to convert bytes to values for a channel.

These dependencies restrict the use of FrameSet to processing LIS data, if they were removed then FrameSet could be used for other file formats but there is no obvious use case for that as, apart from LIS, TotalDepth supports LAS (trivially simple frame sets) and will support RP66 at some point. The latter may trigger a refactoring of the FrameSet module.

FrameSet API Reference

The FrameSet module provides a means of representing LIS frame data.

Created on 10 Jan 2011

exception `TotalDepth.LIS.core.FrameSet.ExceptionFrameSet`
Specialisation of exception for FrameSet.

exception `TotalDepth.LIS.core.FrameSet.ExceptionFrameSetEmpty`
Raised when an illegal operation is performed on a FrameSet.

exception `TotalDepth.LIS.core.FrameSet.ExceptionFrameSetNULLSpacing`
Raised when FrameSet depends on a frame spacing that can not be determined.

exception `TotalDepth.LIS.core.FrameSet.ExceptionFrameSetMixedChannels`
Raised when generating values for multiple channels where the channels are not of the same shape i.e. number of samples, butsts.

`TotalDepth.LIS.core.FrameSet.chkIdx(i, l, msg)`
Global function for checking indexes and raising an IndexError. msg is expected to have two format fields that take i and l respectively.

`TotalDepth.LIS.core.FrameSet.sliceDefaults(theSl)`
Returns a new slice with start=None as 0 and step=None as 1.

class `TotalDepth.LIS.core.FrameSet.DataSeqBase`
Base class for a sequence of objects.

class `TotalDepth.LIS.core.FrameSet.SuChArTe`
Sub-channel Array Template.

numValues
The total number of values in this sub-channel.

index (*theS, theB*)
Returns the index of a particular sample or channel with bounds checking.
WARNING: This not correct for Dipmeter sub-channels.

class `TotalDepth.LIS.core.FrameSet.ChArTe` (*theDsb*)
Channel Array Template. Constructed with a DatumSpecBlock object.

Implementation note: `_index()` and `_dipmeterIndex()` have no bounds checking but are significantly faster for those routines that access then with pre-checked limits.

numSubChannels
Number of sub-channels.

lisSize
Number of bytes per frame in the LIS representation.

subChOffsRange (*sc*)
Returns a range object that is the sub-channel offset in the frame relative to the start of the channel.

subChOffsSlice (*sc, chOfs=0*)
Returns a slice object that is the sub-channel offset in the frame relative to the start of the channel.

index (*theSc, theSa, theBu*)
Returns the index of a particular sub-channel, sample and burst. Order is (fastest changing first): burst, sample. For those with sub-channels: sub-channel, sample This has bounds checking.

dipmeterIndex (*theSc, theSa, theBu*)
Returns dipmeter data index. Bounds checking is performed.

class `TotalDepth.LIS.core.FrameSet.FrameSet` (*theDfsr, theFrameSlice, theChS=None, xAx-isIndex=0*)
Contains the representation of a list of Frames and thus a representation of and 'matrix' (non literal) of: (frame, channel, sub-channel, sample, burst). Commonly shortened to: (fr, ch, sc, sa, bu) Effectively this is a wrapper around a numpy 2-D array that we treat specially to get our 5-D array (LIS channels are not homogeneous).

Constructed with a DFSR, a slice of frame indexes and an optional list of external channel indexes (defaults to all channels). Duplicates in the theChS will be removed and it will be sorted.

xAxisIndex is the external channel index of the X axis (ignored if indirect X).

NUMPY_DATA_TYPE = 'float64'

Data type used in the underlying numpy array.

longStr ()

Returns a long string that describes me.

dumpFrames (*theS*=<_io.TextIOWrapper name='<stdout>' mode='w' encoding='UTF-8'>)

Dump the frames to the stream.

nbytes

Returns the number of bytes in the underlying array implementation.

lisSize

The number of LIS bytes that make up this FrameSet.

numFrames

The number of frames currently in this FrameSet.

valuesPerFrame

The number of values in each frame currently in this FrameSet.

numValues

The total number of values in the array.

frames

Gives access to the raw numpy array.

frame (*fr*)

Returns a specific frame.

xAxisValue (*fr*)

Returns the X axis value for the frame when indirect X is used or None.

xAxisStep (*numFr*)

The distance stepped by numFr.

intFrameNum (*theExtFrameNum*)

Given an external frame number this returns the internal frame number. Will raise an IndexError if the internal frame number is out of range or the external frame number is not in the caller specified slice object.

extFrameNum (*theIntFrameNum*)

Given an internal frame number this returns the external frame number. This does `_not_` test that the internal frame number exists.

numChannels

The number of `_internal_` channels.

numSubChannels (*theChExt*)

Number of sub-channels for an external channel.

numSamples (*theChExt*, *theSc*)

Number of samples for the external channel, sub-channel.

numBursts (*theChExt*, *theSc*)

Number of bursts for the external channel, sub-channel.

isIndirectX

True if there is an indirect X axis, False otherwise.

xAxisDecl

The XAxisDecl object created from the DFSR.

setFrameBytes (*by, fr, chFrom, chTo*)

Given bytes, convert from Rep Codes to 'float64' and populates the appropriate frame and channel(s). This has random write access so the caller needs to be sensitive to the frame and channel location. *fr* is the internal frame position to write the data to. *chFrom*, *chTo* are inclusive and represent external channel indices.

WARNING: It is rare to use this API directly, instead a FrameSet object is usually a member of a LogPass object and that uses this API as a LogPass is capable of finding and reading bytes objects in a file (a LogPass uses RLE and Type01Plan objects to do this efficiently).

setIndirectX (*fr, val*)

Sets an indirect X axis value directly, for example with an EXTRAPOLATE event.

internalChIdx (*chIdxExt*)

Return the internal channel index from the external one.

valueIdxStartExtCh (*ch*)

The index in the frame of the first value for external channel.

valueIdxInFrame (*ch, sc, sa, bu*)

The index in the frame of the value for (external channel, sub-channel, sample, burst). TODO: Provide an API that returns a numpy view of a ch/sc on the frameset.

value (*fr, ch, sc, sa, bu*)

Returns a single value from an: internal *fr*, external *ch*, *sc*, *sa*, *bu*. This is very good at random access but can be quite slow for iteration compared to the generators.

frameView (*chIdxExt, sc*)

Returns a numpy array that is a view of the current frame set for an external channel and sub channel.

genExtChIndexes ()

Generates an ordered list of external channel indexes for this (possibly) partial frameset.

genChScValues (*ch, sc=0, chIsExternal=True*)

Generates values for the external channel and sub channel. *sc* is ignored unless the channel has > 1 sub-channels. If *chIsExternal* is True then *ch* is the external channel index otherwise it is the internal index. The value order is sample/burst.

genChScPoints (*ch, sc=0, chIsExt=True*)

Generates (xAxis, values) as numbers for the external channel and sub-channel. *sc* is ignored unless the channel has > 1 sub-channels. If *chIsExt* is True then *ch* is the external channel index otherwise it is the internal index.

genMultipleChScPoints (*theChScS, chIsExt=True*)

Generates (xAxis, (values, ...)) as numbers for the list of (channel, sub-channel) indexes. An `ExceptionFrameSetMixedChannels` will be raised if all *ch/sc* channels are not of the same form i.e. number of samples and bursts. If *chIsExt* is True then *ch* is the external channel index otherwise it is the internal index.

genAll ()

Yields 6 item tuples (*fr ext, ch ext, sc, sa, bu value*).

accumulate (*theAccs*)

Calls `.add()` on every accumulator (with a unary function) for every internal channel and returns a numpy array of (numSubCh, len(*theAccs*)) doubles. Each accumulator is expected to have `__init__()`, `add()` and `value()` that returns a double implemented. Will raise a `ExceptionFrameSetEmpty` if there are no values to analyse. Will return None if *theAccs* is zero length.

class TotalDepth.LIS.core.FrameSet.**AccMin**
Accumulates the minimum value.

add(*v*)
Add a new value.

value()
Return the result.

class TotalDepth.LIS.core.FrameSet.**AccMax**
Accumulates the maximum value.

add(*v*)
Add a new value.

value()
Return the result.

class TotalDepth.LIS.core.FrameSet.**AccMean**
Accumulates the mean value.

add(*v*)
Add a new value.

value()
Return the result.

class TotalDepth.LIS.core.FrameSet.**AccStDev**
Accumulates the standard deviation.

add(*v*)
Add a new value.

value()
Return the result.

class TotalDepth.LIS.core.FrameSet.**AccCount**
Accumulates the number of values.

add(*v*)
Add a new value.

value()
Return the result.

class TotalDepth.LIS.core.FrameSet.**AccDelta**
Base class for accumulating a count of first order differences.

add(*v*)
Add a new value.

value()
Return the result.

class TotalDepth.LIS.core.FrameSet.**AccInc**
Counting how many values are an increase from the previous value.

add(*v*)
Add a new value.

class TotalDepth.LIS.core.FrameSet.**AccEq**
Counting how many values are equal to the previous value.

add(*v*)
Add a new value.

class TotalDepth.LIS.core.FrameSet.**AccDec**
Counting how many values are less than the previous value.

add(*v*)
Add a new value.

class TotalDepth.LIS.core.FrameSet.**AccBias**
Measures increment, equal, decrement and computes bias which is: $(inc - dec) / total$.

add(*v*)
Add a new value.

value()
Return the result.

class TotalDepth.LIS.core.FrameSet.**AccDrift**
Measures drift i.e. the movement between the first and the last value.

add(*v*)
Add a new value.

value()
Return the result.

class TotalDepth.LIS.core.FrameSet.**AccActivity**
Measures curve activity.

add(*v*)
Add a new value.

value()
Return the result.

FrameSet Usage

Run Length Encoding Module

The RLE module provides Run Length Encoding suitable for recording the file positions of a set of LIS Logical Records that represent frame data.

Created on 5 Jan 2011

class RLEItem()

A generic item in a Run Length Encoding list.

class RLE()

A generic Run Length Encoding list.

class RLEItemType01()

A specialised item in a Run Length Encoding list for type 0/1 LIS Logical Records.

class RLEType01()

A specialised Run Length Encoding list for type 0/1 LIS Logical Records.

API Reference**class** TotalDepth.LIS.core.Rle.**RLEItem**(*v*)

Class that represents a single entry in a Run Length Encoding set. *v* - The datum value.

__str__()

String representation.

datum

The initial datum value.

stride

The stride as a number or None if there is only one entry.

repeat

The repeat count.

numValues()

Total number of record values.

add(*v*)

Returns True if *v* has been absorbed in this entry. False means a new entry is required.

values()

Generates all values.

value(*i*)

Returns a particular value.

range()

Returns a range object that has (start, stop, step) or None if a single entry.

first()

Returns the first value.

last()

Returns the last value.

__weakref__

list of weak references to the object (if defined)

class TotalDepth.LIS.core.Rle.**RLE**(*theFunc=None*)

Class that represents Run Length Encoding.

theFunc - optional unary function to convert all values with.

__init__(*theFunc=None*)

Constructor, optionally takes a unary function to convert all values with.

__str__()

String representation.

__len__()

The number of RLEItem(s).

__getitem__(*key*)

Returns a RLEItem.

numValues ()
Total number of record values.

add (*v*)
Adds a value to this RLE object.

values ()
Generates all values entered.

value (*i*)
Indexing; this returns the *i*'th value added.

rangeList ()
Returns a list of range() or None objects. A None object means that the RLEItem has a single value.

first ()
Returns the first value or None if no values added.

last ()
Returns the last value or None if no values added.

__weakref__
list of weak references to the object (if defined)

class TotalDepth.LIS.core.Rle.**RLEItemType01** (*tellLrPos, numFrameS, xAxisValue*)
Specialisation of an RLEItem for type 0 and type 1 LIS Logical Records. This is a RLEItem for the Logical Record but within we have a RLE() object for the X axis values.

tellLrPos - the position in the LIS file of the start of the Logical Record.

numFrameS - integer number of frames in this Logical Record.

xAxisValue - The value of the X axis of the first frame in the Logical Record.

__str__ ()
String representation.

numFrames
Total number of frames.

add (*tellLrPos, numFrameS, xAxisValue*)
Returns True if *v* has been absorbed in this entry. False means a new entry is required. A new entry is required if the tellLrPos is not regular or numFrameS is different than before.

values ()
Generates ordered tuples of (value, number of frames, xaxis value).

value (*i*)
Returns the *i*'th tuple of (i, (value, number of frames, xaxis value)).

totalFrames ()
Returns the total number of frames in this RLE item.

tellLrForFrame (*fNum*)
Returns the Logical Record position that contains the integer frame number.

xAxisFirst ()
Returns the first X-axis value loaded.

xAxisLast ()
Returns the first X-axis value loaded.

class TotalDepth.LIS.core.Rle.**RLEType01** (*theXUnits, *args*)
Class that represents Run Length Encoding for type 0/1 logical records.

theXUnits - the X axis units.

__str__()
String representation.

xAxisUnits
X axis units.

hasXaxisData
True if there is X axis data.

add (*tellLrPos*, *numFrameS*, *xAxisValue*)
Adds a value to this RLE object.

tellLrForFrame (*fNum*)
Returns the (*lr_seek*, *frame_offset*) i.e. the Logical Record position that contains the integer frame number and the number of excess frames.

totalFrames ()
Returns the total number of frames in this RLE object.

xAxisFirst ()
Returns the first X-axis value loaded or None if nothing loaded.

xAxisLast ()
Returns the last X-axis value at the start of the last Logical Record loaded or None if nothing loaded.

xAxisLastFrame ()
Returns the last X-axis value of the last frame loaded or None if nothing loaded.

frameSpacing ()
Returns the frame spacing from the first/last entries, or None if nothing loaded. Returned value is -ve for decreasing X (up logs), +ve for increasing X (down and time logs).

Type01Plan

Given a DFSR the FrameSetPlan gives offsets to any part of the Logical Record for any frame and channel.

exception `TotalDepth.LIS.core.Type01Plan.ExceptionFrameSetPlan`
Specialisation of exception for FrameSetPlan.

exception `TotalDepth.LIS.core.Type01Plan.ExceptionFrameSetPlanNegLen`
Specialisation of exception for negative/too small length arguments to FrameSetPlan.

exception `TotalDepth.LIS.core.Type01Plan.ExceptionFrameSetPlanOverrun`
Exception channel number greater than available.

`TotalDepth.LIS.core.Type01Plan.EVENT_READ = 'read'`
Read event

`TotalDepth.LIS.core.Type01Plan.EVENT_SKIP = 'skip'`
Skip event

`TotalDepth.LIS.core.Type01Plan.EVENT_EXTRAPOLATE = 'extrapolate'`
Extrapolate event

class `TotalDepth.LIS.core.Type01Plan.FrameSetPlan` (*dfsr*)
Given a DFSR the FrameSetPlan gives offsets to any part of the frame set within a Logical Record.

NOTE: All offsets, lengths etc. are relative to the end of the LRH i.e. add `LR_HEADER_LENGTH` to get absolute Logical Data position.

indirectSize

The size, in bytes of the indirect X axis value. 0 for explicit X axis.

frameSize

Frame size in bytes.

numChannels

Number of channels.

channelSize (*i*)

The size of the given channel.

numFrames (*recLen*)

Returns the number of frames that will fit into the record length. May raise a `ExceptionFrameSetPlan`. May raise `ExceptionFrameSetPlanNegLen` if arguments are negative.

NOTE: record length should not include size of LRH.

chOffset (*frame, ch*)

Returns the offset into the LR (after LRH) to the start of a particular channel and frame.

Will raise `ExceptionFrameSetPlanNegLen` if arguments are negative or an `IndexError` if *ch* out of range.

skipToEndOfFrame (*ch*)

Returns the skip distance into the LR to the end of frame after a particular channel.

genOffsets (*theChIndexS*)

Yields an indefinite set of (*frame, channel, offset*) values for the set of channels. Will raise `ExceptionFrameSetPlanNegLen` if any channel negative. Will raise `KeyError` if any channel index is out of range.

__weakref__

list of weak references to the object (if defined)

genEvents (*theFSlice, theChIndexS*)

For a single Logical Record type 0/1 this yields an set of events.

theFSlice is a frame slice object (default *start*=0, *step*=1), *step* 0 is interpreted as *step* 1.

theChIndexS is as list of indexes of channels that need to be read.

The events are 5 member tuples: (*event_type, size, frame, channel_start, channel_stop*)

event_type is 'skip' or 'read' or 'extrapolate':

skip: ('skip', *size, frame_number, channel_start, channel_stop*)

read: ('read', *size, frame_number, channel_start, channel_stop*)

extrapolate: ('extrapolate', *frames, frame_number, None, None*)

NOTE: No 'seek', 0, ... events are generated.

size is the number of bytes to read or skip or, for 'extrapolate' the number of frames to extrapolate the implied X axis.

frame_number is the frame number in the predicted Logical Record.

In the case of 'skip' or 'extrapolate' its is the frame number in the Logical Record being moved to. The frame number can be None if there is no prediction, for example when reading an indirect X at the beginning of an LR.

channel_start, channel_stop are the channel numbers (inclusive) in the DFSR DSB block None being the indirect X axis.

Thus: ('read', *size, frame_number, None, 3*) Means read *size* bytes and interpret them as channels: None, 0, 1, 2, 3. 'extrapolate' events mean project the Xaxis forward by the specified number of frames (this

will not be bestrided with two seek events but preceded or followed by a single seek event (if any). 'read' and 'seek' events are synchronous as are 'read' and 'extrapolate'. However 'seek' and 'extrapolate' are asynchronous i.e. 'seek'-'extrapolate' is equivalent to 'extrapolate'-'seek'.

Will raise `ExceptionFrameSetPlanNegLen` if any channel negative or `fStop < fStart`. Will raise `IndexError` if any channel index is out of range.

Be aware: This code is tricky.

1.11.2 TotalDepth.LAS API Reference

Contents:

LAS Read

Reads LAS files.

Created on Jan 11, 2012

exception `TotalDepth.LAS.core.LASRead.ExceptionLASRead`

Specialisation of exception for LASRead.

exception `TotalDepth.LAS.core.LASRead.ExceptionLASReadSection`

Specialisation of exception for LASRead when handling sections.

exception `TotalDepth.LAS.core.LASRead.ExceptionLASReadSectionArray`

Specialisation of exception for LASRead when handling array section.

exception `TotalDepth.LAS.core.LASRead.ExceptionLASReadData`

Specialisation of exception for LASRead when reading data.

exception `TotalDepth.LAS.core.LASRead.ExceptionLASKeyError`

Equivalent to `KeyError` when looking stuff up.

`TotalDepth.LAS.core.LASRead.LAS_FILE_EXT = '.las'`

LAS file extension

`TotalDepth.LAS.core.LASRead.LAS_FILE_EXT_LOWER = '.las'`

LAS lower case file extension

`TotalDepth.LAS.core.LASRead.hasLASExtension(fp)`

Returns True if the file extension is a LAS one.

`TotalDepth.LAS.core.LASRead.RE_COMMENT = re.compile('^\\s*#(\\.*)$')`

Regex to match a comment

`TotalDepth.LAS.core.LASRead.DEBUG_LINE_BY_LINE = False`

logging.debug call here can add about 50% of the processing time

`TotalDepth.LAS.core.LASRead.genLines(f)`

Given an file-like object this generates non-blank, non-comment lines. It's a co-routine so can accept a line to put back.

`TotalDepth.LAS.core.LASRead.SECT_TYPES = 'VWCPOA'`

All section identifiers

`TotalDepth.LAS.core.LASRead.SECT_TYPES_WITH_DATA_LINES = 'VWCP'`

Section with data lines

`TotalDepth.LAS.core.LASRead.SECT_TYPES_WITH_INDEX = 'VWCPA'`

Section with index value in column 0

`TotalDepth.LAS.core.LASRead.RE_SECT_HEAD = re.compile('^~([VWCPOA])(.+)*$')`
 Regex to match a section head

`TotalDepth.LAS.core.LASRead.SECT_DESCRIPTION_MAP = {'V': 'Version Information Section', 'W': 'Well Information Section'}`
 Map of section identifiers to description

`TotalDepth.LAS.core.LASRead.RE_LINE_FIELD_0 = re.compile('^\\s*([^ .:]+)\\s*$')`
 The 'MENM' field, no spaces, dots or colons. ONE group

`TotalDepth.LAS.core.LASRead.RE_LINE_FIELD_1 = re.compile('^([^ :]+)*(.)+$')`
 The data field which is the middle of the line between the first '.' and last '.' This is composed of optional units and value. Units must follow the dot immediately and contain no colons or spaces Note: Group 2 may have leading and trailing spaces TWO groups

`TotalDepth.LAS.core.LASRead.RE_LINE_FIELD_2 = re.compile("\n ^ # Start of line\n ([^{|}]+)*")`
 Data field 2 is after the last '.' THREE groups

class `TotalDepth.LAS.core.LASRead.SectLine(mnem, unit, valu, desc, format, assoc)`

Captures the 6 fields: mnem unit valu desc format assoc

`__getnewargs__()`
 Return self as a plain tuple. Used by copy and pickle.

static `__new__(_cls, mnem, unit, valu, desc, format, assoc)`
 Create new instance of SectLine(mnem, unit, valu, desc, format, assoc)

`__repr__()`
 Return a nicely formatted representation string

assoc
 Alias for field number 5

desc
 Alias for field number 3

format
 Alias for field number 4

mnem
 Alias for field number 0

unit
 Alias for field number 1

valu
 Alias for field number 2

class `TotalDepth.LAS.core.LASRead.LASSection(sectType)`

Contains data on a section.

`__len__()`
 Number of members.

`__contains__(theMnem)`
 Membership test.

addMemberLine (*i*, *l*)
 Given a line this decomposes it to its _members. i is the position of the line l in the file.

finalise ()
 Finalisation of section, this updates the internal representation.

`__getitem__(key)`
 Returns an entry, key can be int or str.

mnemS()

Returns an list of mnemonics.

unitsS()

Returns an list of mnemonic units.

keys()

Returns the keys in the internal map.

find(*m*)

Returns the member ordinal for mnemonic *m* or -1 if not found. This can be used for finding the array column for a particular curve.

__weakref__

list of weak references to the object (if defined)

class TotalDepth.LAS.core.LASRead.LASSectionArray(*sectType*, *wrap*, *curvSect*, *null*=-999.25)

Contains data on an array section.

addMemberLine(*i*, *l*)

Process a line in an array section.

finalise()

Finalisation. TODO: Make a numpy array and get rid of the members. Need to overload `__getitem__`.

frameSize()

Returns the number of data points in a frame.

class TotalDepth.LAS.core.LASRead.LASBase(*id*)

Base class for LAS reading and writing. This provides common functionality to child classes.

UNITS_LAS_TO_LIS = {'F': 'FEET', 'mts': 'M' }

Mapping of commonly seen LAS units to proper LIS units Both key and value must be strings

__len__()

Number of sections.

__getitem__(*key*)

Returns a section, key can be int or str.

numFrames()

Returns the number of frames of data in an 'A' record if I have one.

numDataPoints()

Returns the number of frame data points in an 'A' record if I have one.

genSects()

Yields up each section.

nullValue

The NULL value, defaults to -999.25.

xAxisUnits

The X axis units.

xAxisStart

The Xaxis start value as an EngVal.

xAxisStop

The Xaxis end value as an EngVal.

xAxisStep

The Xaxis step value as an EngVal.

logDown ()

Returns True if X axis is increasing i.e. for time or down log.

getWsdMnem (m)

Returns a tuple of (value, units) for a Mnemonic that may appear in either a Well section or a Parameter section. Units may be None if empty. Returns (None, None) if nothing found.

getAllWsdMnemonics ()

Returns a set of mnemonics from the Well section and the Parameter section.

hasOutpMnem (theMnem)

Returns True if theMnem, a Mnem.Mnem() object is an output in the Curve section. It will use the alternate names table LGFORMAT_LAS from LASConstants to interpret curves that are not exact matches.

curveMnems (ordered=False)

Returns list of curve names actually declared in the Curve section. List will be unordered if ordered is False.

curveUnitsAsStr (m)

Given a curve as a Mnem.Mnem() this returns the units as a string. May raise KeyError.

genOutpPoints (theMnem)

Generates curve values for theMnem, a Mnem.Mnem() object.

__weakref__

list of weak references to the object (if defined)

class TotalDepth.LAS.core.LASRead.**LASRead** (theFp, theFileID=None)

Reads a LAS file.

__init__ (theFp, theFileID=None)

Reads a LAS file from theFp that is either a string (file path) or a file like object.

1.11.3 Utility Package Reference

Contents:

Common Command Line Options

Common command line options, this is to try and present some degree of interface consistency among command line applications.

Copyright (c) 2010-2011 Paul Ross. All rights reserved.

TotalDepth.util.CmnCmdOpts.**argParser** (desc, prog=None, version=None)

Return an command line parser with the standard pre-set options.

Standard options are -h, --version and:

-j: Multiprocessing job control.

-k: Flag to indicate that we should keep going as far as sensible.

-l: Log level.

TotalDepth.util.CmnCmdOpts.**argParserIn** (*args, **kwargs)

Return an command line parser with the standard pre-set options plus an input path as an argument.

TotalDepth.util.CmnCmdOpts.**argParserInOut** (*args, **kwargs)

Return an command line parser with the standard pre-set options plus an input and output paths as an arguments.

DictTree

A dictionary that takes a list of hashables as a key and behaves like a tree.

exception `TotalDepth.util.DictTree.ExceptionDictTree`
Exception when handling a DictTree object.

class `TotalDepth.util.DictTree.DictTree` (*valIterable=None*)
A dictionary that takes a list of hashables as a key and behaves like a tree

add (*k, v*)
Add a key/value. *k* is a list of hashables.

remove (*k, v=None*)
Remove a key/value. *k* is a list of hashables.

value (*k*)
Value corresponding to a key or None. *k* is a list of hashables.

values ()
Returns a list of all values.

keys ()
Return a list of keys where each key is a list of hashables.

__len__ ()
Returns the number of keys.

depth ()
Returns the maximum tree depth as an integer.

__weakref__
list of weak references to the object (if defined)

class `TotalDepth.util.DictTree.DictTreeHtmlTable` (**args*)

A sub-class of DictTree that helps writing HTML row/col span tables Suppose we have a tree like this:

```

                                     | - AAA
                                     |
                               | - AA --| - AAB
                               |         |
                               |         | - AAC
Root  ---| - A ---|
        |         | - AB
        |         | - AC ---- ACA
        |         |
        | - B
        |
        | - C ---- CA ---- CAA
```

And we want to represent the tree like this when laid out as an HTML table:

| | | |
|-------|-------|-------|
| ----- | | |
| A | AA | AAA |
| | | ----- |
| | | AAB |
| | | ----- |
| | | AAC |
| | ----- | |
| | AB | |

| | | |
|-------|-------|-----|
| | ----- | |
| | AC | ACA |
| ----- | | |
| B | | |
| ----- | | |
| C | CA | CAA |
| ----- | | |

In this example the tree is loaded branch by branch thus: `myTree = DictTreeHtmlTable()` `myTree.add(('A', 'AA', 'AAA'), None)` `myTree.add(('A', 'AA', 'AAB'), None)` `myTree.add(('A', 'AA', 'AAC'), None)` `myTree.add(('A', 'AB'), None)` `myTree.add(('A', 'AC', 'ACA'), None)` `myTree.add(('B'), None)` `myTree.add(('C', 'CA', 'CAA'), None)`

The HTML code generator can be used like this:

```
# Write: <table border="2" width="100%">
for anEvent in myTree.genColRowEvents():
    if anEvent == myTree.ROW_OPEN:
        # Write out the '<tr>' element
    elif anEvent == myTree.ROW_CLOSE:
        # Write out the '</tr>' element
    else:
        k, v, r, c = anEvent
        # Write '<td rowspan="%d" colspan="%d">%s</td>' % (r, c, v)
# Write: </table>
```

And the HTML will look like this:

```
<table border="2" width="100%">
  <tr valign="top">
    <td rowspan="5">A</td>
    <td rowspan="3">AA</td>
    <td>AAA</td>
  </tr>
  <tr valign="top">
    <td>AAB</td>
  </tr>
  <tr valign="top">
    <td>AAC</td>
  </tr>
  <tr valign="top">
    <td colspan="2">AB</td>
  </tr>
  <tr valign="top">
    <td>AC</td>
    <td>ACA</td>
  </tr>
  <tr valign="top">
    <td colspan="3">B</td>
  </tr>
  <tr valign="top">
    <td>C</td>
    <td>CA</td>
    <td>CAA</td>
  </tr>
</table>
```

setColRowSpan()

Top level call that sets colspan and rowspan attributes.

genColRowEvents ()

Returns a set of events that are quadruples. (key_branch, value, rowspan_int, colspan_int) The branch is a list of keys the from the branch of the tree. The rowspan and colspan are both integers. At the start of the a <tr> there will be a ROW_OPEN and at row end (</tr> a ROW_CLOSE will be yielded

Directory Walking

Provides various ways of walking a directory tree

Created on Jun 9, 2011

class TotalDepth.util.DirWalk.**FileInOut** (*filePathIn, filePathOut*)

A pair of (in, out) file paths

__getnewargs__ ()

Return self as a plain tuple. Used by copy and pickle.

static **__new__** (*_cls, filePathIn, filePathOut*)

Create new instance of FileInOut(filePathIn, filePathOut)

__repr__ ()

Return a nicely formatted representation string

filePathIn

Alias for field number 0

filePathOut

Alias for field number 1

exception TotalDepth.util.DirWalk.**ExceptionDirWalk**

Exception class for this module.

TotalDepth.util.DirWalk.**genBigFirst** (*d*)

Generator that yields the biggest files (name not path) first. This is fairly simple in that it only looks the current directory not only sub-directories. Useful for multiprocessing.

TotalDepth.util.DirWalk.**dirWalk** (*theIn, theOut=None, theFnMatch=None, recursive=False, bigFirst=False*)

Walks a directory tree generating file paths.

theIn - The input directory.

theOut - The output directory. If None then input file paths as strings will be generated If non-None this function will yield FileInOut(in, out) objects. NOTE: This does not create the output directory structure, it is up to the caller to do that.

theFnMatch - A glob like match pattern for file names (not tested for directory names).

recursive - Boolean to recurse or not.

bigFirst - If True then the largest files in directory are given first. If False it is alphabetical.

Timing Code Execution

Has classes for timing execution

exception TotalDepth.util.ExecTimer.**ExceptionExecTimer**

Specialisation of exception for this module.

class TotalDepth.util.ExecTimer.**ExecEvent** (*desc*)

Records the timing of a single event.

stop (*bytes=0*)

Stop the timer.

hasCompleted

True if the timer has been stopped.

tExec

Executions time in seconds.

lenDesc ()

Length of the task description string.

writeToStderr (*descWidth=0*)

Write self to sys.stderr.

writeToStream (*theS, descWidth=0*)

Write self to provided stream.

__weakref__

list of weak references to the object (if defined)

class TotalDepth.util.ExecTimer.**ExecTimerList**

Maintains a list of execution time objects

__init__ ()

Constructor

__len__ ()

Number of task timers.

startNewTimer (*theDesc*)

Load a new task timer starting right now.

timer

The current timer.

hasActiveTimer

True if there is a running timer, False if there are either no timers or the latest timer is halted.

stopTimer (*bytes=0*)

Stop current timer.

writeToStderr ()

Write self to sys.stderr.

writeToStream (*theS*)

Write self to provided stream.

__weakref__

list of weak references to the object (if defined)

Look-ahead File Buffer

Provides a ‘look ahead’ file buffer where the caller can inspect bytes ahead of the current position.

Created on Oct 26, 2011

exception TotalDepth.util.FileBuffer.**ExceptionFileBuffer**

Specialisation of Exception for the FileBuffer module.

`__weakref__`

list of weak references to the object (if defined)

exception `TotalDepth.util.FileBuffer.ExceptionFileBufferEOF`

Specialisation of Exception for the FileBuffer EOF.

class `TotalDepth.util.FileBuffer.FileBuffer(f)`

Provides a buffer interface to a file where the user can look ahead any distance from the current position.

`tell()`

Current file position.

`step()`

Increment the file position by one byte, returns the byte just read.

`__getitem__(i)`

Get an arbitrary byte or slice.

`__weakref__`

list of weak references to the object (if defined)

Histogram

Produces histograms.

Created on Nov 29, 2011

class `TotalDepth.util.Histogram.Histogram`

A histogram class.

`add(x, count=1)`

Increments the count of value x by count (default 1).

`__getitem__(x)`

Returns the current count of x.

`strRep(width=75, chr='+', valTitle='', inclCount=False)`

Returns a string representation of the histogram in ASCII.

width - The maximum width to use.

chr - The character to use in the plot.

valTitle - The title to use for values.

inclCount - Include the tecture count for each value?

`__weakref__`

list of weak references to the object (if defined)

Testing

Tests are in `test/TestHistogram.py`

Running Tests

```
$ python3 test/testHistogram.py
```


Test Coverage

```
$ coverage run test/testHistogram.py
...
$ coverage report -m
```

Examples

```
from TotalDepth.util import Histogram

myH = Histogram.Histogram()
for x in range(1, 12):
    self._hist.add(x, x)
print(self._hist.strRep())
# Prints """ 1 | ++++++
2 | ++++++
3 | ++++++
4 | ++++++
5 | ++++++
6 | ++++++
7 | ++++++
8 | ++++++
9 | ++++++
10 | ++++++
11 | ++++++ """
```

HTML Utilities

HTML utility functions.

TotalDepth.util.HtmlUtils.**retHtmlFileName** (*thePath*)

Creates a unique, short, human readable file name base on the input file path.

TotalDepth.util.HtmlUtils.**retHtmlFileLink** (*theSrcPath*, *theLineNum*)

Returns a link to a file/line.

TotalDepth.util.HtmlUtils.**writeHtmlFileLink** (*theS*, *theSrcPath*, *theLineNum*, *theText*=",
theClass=None)

Writes a link to another HTML file that represents source code. *theS* is an XHTML stream. *theSrcPath* is the path of the original source, which will be encoded with `retHtmlFileName()`. *theLineNum* is an integer line number in the target. *theText* is optional navigation text. *theClass* is optional CSS class for the navigation text.

TotalDepth.util.HtmlUtils.**writeHtmlFileAnchor** (*theS*, *theLineNum*, *theText*=", *theClass=None*)

Write an anchor to the stream.

TotalDepth.util.HtmlUtils.**pathSplit** (*p*)

Split a path into its components.

TotalDepth.util.HtmlUtils.**writeFileListAsTable** (*theS*, *theFileLinkS*, *tableAttrs*, *includeKeyTail*)

Writes a list of file names as an HTML table looking like a directory structure. *theFileLinkS* is a list of pairs (file_path, href). The navigation text in the cell will be the basename of the file_path.

`TotalDepth.util.HtmlUtils.writeFileListTrippleAsTable` (*theS, theFileLinkS, tableAttrs, includeKeyTail*)

Writes a list of file names as an HTML table looking like a directory structure. *theFileLinkS* is a list of triples (file_name, href, nav_text).

`TotalDepth.util.HtmlUtils.writeDictTreeAsTable` (*theS, theDt, tableAttrs, includeKeyTail*)

Writes a DictTreeHtmlTable object as a table, for example as a directory structure.

The key list in the DictTreeHtmlTable object is the path to the file i.e. `os.path.abspath(p).split(os.sep)` and the value is expected to be a pair of (link, nav_text) or None.

`TotalDepth.util.HtmlUtils.writeFilePathsAsTable` (*valueType, theS, theKvS, tableStyle, fnTd*)

Writes file paths as a table, for example as a directory structure.

valueType - The type of the value: None | 'list' | 'set'

theKvS - A list of pairs (file_path, value).

tableStyle - The style used for the table.

fnTd - A callback function that is executed for a <td> element when there is a non-None value. This is called with the following arguments:

- *theS* - The HTML stream.
- *attrs* - A map of attrs that include the rowspan/colspan for the <td>
- *k* - The key as a list of path components.
- *v* - The value given by the caller.

XML Writer Module

Introduction

The important classes here are:

- `XmlWrite.XMLStream` (and derived classes): these manage the low level stream output.
- `XmlWrite.XMLElement`: these handles opening and closing elements via the Context Manager. They require an initialised XMLStream in their constructor.

Together, if used correctly, these make writing output to a stream fluent in the code. They also make strong guarantees about the encoding and well-formedness of the result.

Reference

Writes XML and XHTML.

exception `TotalDepth.util.XmlWrite.ExceptionXml`

Exception specialisation for the XML writer.

exception `TotalDepth.util.XmlWrite.ExceptionXmlEndElement`

Exception specialisation for end of element.

`TotalDepth.util.XmlWrite.encodeString` (*theS, theCharPrefix='_'*)

Returns a string that is the argument encoded. RFC3548:

| Table 1: The Base 64 Alphabet | | | |
|-------------------------------|----------|-------|----------|
| Value | Encoding | Value | Encoding |
| 0 | A | 17 | R |
| 1 | B | 18 | S |
| 2 | C | 19 | T |
| 3 | D | 20 | U |
| 4 | E | 21 | V |
| 5 | F | 22 | W |
| 6 | G | 23 | X |
| 7 | H | 24 | Y |
| 8 | I | 25 | Z |
| 9 | J | 26 | a |
| 10 | K | 27 | b |
| 11 | L | 28 | c |
| 12 | M | 29 | d |
| 13 | N | 30 | e |
| 14 | O | 31 | f |
| 15 | P | 32 | g |
| 16 | Q | 33 | h |
| | | 34 | i |
| | | 35 | j |
| | | 36 | k |
| | | 37 | l |
| | | 38 | m |
| | | 39 | n |
| | | 40 | o |
| | | 41 | p |
| | | 42 | q |
| | | 43 | r |
| | | 44 | s |
| | | 45 | t |
| | | 46 | u |
| | | 47 | v |
| | | 48 | w |
| | | 49 | x |
| | | 50 | y |
| | | 51 | z |
| | | 52 | 0 |
| | | 53 | 1 |
| | | 54 | 2 |
| | | 55 | 3 |
| | | 56 | 4 |
| | | 57 | 5 |
| | | 58 | 6 |
| | | 59 | 7 |
| | | 60 | 8 |
| | | 61 | 9 |
| | | 62 | + |
| | | 63 | / |
| | | | (pad) = |

See section 3 of : <http://www.faqs.org/rfcs/rfc3548.html>

TotalDepth.util.XmlWrite.**decodeString** (*theS*)

Returns a string that is the argument decoded. May raise a TypeError.

TotalDepth.util.XmlWrite.**nameFromString** (*theStr*)

Returns a name from a string.

See <http://www.w3.org/TR/1999/REC-html401-19991224/types.html#type-cdata>

“ID and NAME tokens must begin with a letter ([A-Za-z]) and may be followed by any number of letters, digits ([0-9]), hyphens (“-”), underscores (“_”), colons (“:”), and periods (“.”).

This also works for in namespaces as ‘:’ is not used in the encoding.

class TotalDepth.util.XmlWrite.**XmlStream** (*theFout*, *theEnc*=‘utf-8’, *theDtdLocal*=None, *theId*=0)

Creates and maintains an XML output stream.

__init__ (*theFout*, *theEnc*=‘utf-8’, *theDtdLocal*=None, *theId*=0)

Initialise with a writable file like object or a file path.

theFout - The file-like object or a string. If the latter it will be closed on **__exit__**.

theEnc - The encoding to be used.

theDtdLocal - Any local DTD as a string.

id - An integer value to use as an ID string.

id

A unique ID in this stream. The ID is incremented on each call.

xmlSpacePreserve ()

Suspends indentation for this element and its descendants.

characters (*theString*)

Encodes the string and writes it to the output.

literal (*theString*)

Writes theString to the output without encoding.

comment (*theS*)

Writes a comment to the output stream.

pI (*theS*)

Writes a Processing Instruction to the output stream.

endElement (*name*)

Ends an element.

writeECMAScript (*theScript*)

Writes the ECMA script.

Example:

```
<script type="text/ecmascript">
//<![CDATA[
...
// ]]>
</script>
```

__enter__ ()

Context manager support.

__exit__ (*exc_type, exc_value, traceback*)

Context manager support.

__weakref__

list of weak references to the object (if defined)

class TotalDepth.util.XmlWrite.**Element** (*theXmlStream, theElemName, theAttrs=None*)

Represents an element in a markup stream.

__enter__ ()

Context manager support.

__weakref__

list of weak references to the object (if defined)

__exit__ (*excType, excValue, tb*)

Context manager support.

Examples

All these examples assume these imports:

```
import io
from TotalDepth.util import XmlWrite
```

Creating an XML Stream

Create a file-like object and write to it using an `XmlWrite.XmlStream`:

```
myF = io.StringIO()
with XmlWrite.XmlStream(myF) :
    pass
print(myF.getvalue())
# Results in:
<?xml version='1.0' encoding="utf-8"?>\n
```

Simple Elements

Create a file-like object and write elements to it using an `XmlWrite.XmlElement`:

```
myF = io.StringIO()
with XmlWrite.XmlStream(myF) as xS:
    with XmlWrite.Element(xS, 'Root', {'version' : '12.0'}):
        with XmlWrite.Element(xS, 'A', {'attr_1' : '1'}):
            pass
print(myF.getvalue())
# Results in:
<?xml version='1.0' encoding="utf-8"?>
<Root version="12.0">
  <A attr_1="1"/>
</Root>
```

Mixed Content

As above but writing text as well:

```
myF = io.StringIO()
with XmlWrite.XmlStream(myF) as xS:
    with XmlWrite.Element(xS, 'Root', {'version' : '12.0'}):
        with XmlWrite.Element(xS, 'A', {'attr_1' : '1'}):
            xS.characters('<&>')
print(myF.getvalue())
# Results in:
<?xml version='1.0' encoding="utf-8"?>
<Root version="12.0">
  <A attr_1="1">&lt;&amp;&gt;&gt;</A>
</Root>
```

Testing

The unit tests are in `test/TestWMLWrite.py`.

Plot Package Reference

Contents:

Plot Coordinates

Main Classes

Most classes in this module are `collections.namedtuple` objects.

| Class | Description | Attributes |
|--------|------------------------------|-------------------------|
| Dim | Linear dimension | value units |
| Box | A Box | width depth |
| Pad | Padding around a tree object | prev next, parent child |
| Margin | Padding around an object | left right top bottom |
| Pt | A point in Cartesian space | x y |

Reference

Provides a fairly basic two dimensional coordinate system.

exception TotalDepth.util.plot.Coord.**ExceptionCoord**
Exception class for representing Coordinates.

exception TotalDepth.util.plot.Coord.**ExceptionCoordUnitConvert**
Exception raised when converting units.

TotalDepth.util.plot.Coord.**BASE_UNITS** = 'px'
Base units for dimensions

TotalDepth.util.plot.Coord.**UNIT_MAP** = {None: 1.0, 'px': 1.0, 'pt': 1.0, 'pc': 12.0, 'in': 12.0}
Map of {unit name : conversion factor to base units, ... }

TotalDepth.util.plot.Coord.**units**()
Returns the unsorted list of acceptable units.

TotalDepth.util.plot.Coord.**convert**(val, unitFrom, unitTo)
Convert a value from one set of units to another.

class TotalDepth.util.plot.Coord.**Dim**
Represents a dimension as an engineering value i.e. a number and units.

scale(factor)
Returns a new Dim() multiplied by a factor, units are unchanged.

divide(factor)
Returns a new Dim() divided by a factor, units are unchanged.

convert(u)
Returns a new Dim() with units changed and value converted.

__add__(other)
Overload self+other, returned result has the sum of self and other. The units chosen are self's unless self's units are None in which case other's units are used (if not None).

__sub__(other)
Overload self-other, returned result has the difference of self and other. The units chosen are self's unless self's units are None in which case other's units are used (if not None).

__iadd__(other)
Addition in place, value of other is converted to my units and added.

__isub__(other)
Subtraction in place, value of other is subtracted.

__lt__(other)
Returns true if self value < other value after unit conversion.

__le__(other)
Returns true if self value <= other value after unit conversion.

`__eq__(other)`
Returns true if self value == other value after unit conversion.

`__ne__(other)`
Returns true if self value != other value after unit conversion.

`__gt__(other)`
Returns true if self value > other value after unit conversion.

`__ge__(other)`
Returns true if self value >= other value after unit conversion.

`TotalDepth.util.plot.Coord.dimIn(v)`
Returns a Dim object with the value in inches.

class `TotalDepth.util.plot.Coord.Box`
A named tuple that describes a box with width and depth as Dim() objects.

`__str__()`
Stringifying.

class `TotalDepth.util.plot.Coord.Pad`
Padding around another object that forms the Bounding Box. All 4 attributes are Dim() objects

`__str__()`
Stringifying.

class `TotalDepth.util.plot.Coord.Margin`
Margin padding around another object. All 4 attributes are Coord.Dim() objects.

`__str__()`
Stringifying.

class `TotalDepth.util.plot.Coord.Pt`
A point, an absolute x/y position on the plot area. Members are Coord.Dim().

`__eq__(other)`
Comparison.

`__str__()`
Stringifying.

convert (*u*)
Returns a new Pt() with units changed and value converted.

scale (*factor*)
Returns a new Pt() scaled by a factor, units are unchanged.

`TotalDepth.util.plot.Coord.baseUnitsDim(theLen)`
Returns a Coord.Dim() of length and units BASE_UNITS.

`TotalDepth.util.plot.Coord.zeroBaseUnitsDim()`
Returns a Coord.Dim() of zero length and units BASE_UNITS.

`TotalDepth.util.plot.Coord.zeroBaseUnitsBox()`
Returns a Coord.Box() of zero dimensions and units BASE_UNITS.

`TotalDepth.util.plot.Coord.zeroBaseUnitsPad()`
Returns a Coord.Pad() of zero dimensions and units BASE_UNITS.

`TotalDepth.util.plot.Coord.zeroBaseUnitsPt()`
Returns a Coord.Dim() of zero length and units BASE_UNITS.

TotalDepth.util.plot.Coord.**newPt** (*theP, incX=None, incY=None*)

Returns a new Pt object by incrementing existing point incX, incY that are both Dim() objects or None.

TotalDepth.util.plot.Coord.**convertPt** (*theP, theUnits*)

Returns a new point with the dimensions of theP converted to theUnits.

Examples

Coord.Dim()

Creation, addition and subtraction:

```
d = Coord.Dim(1, 'in') + Coord.Dim(18, 'px')
# d is 1.25 inches
d = Coord.Dim(1, 'in') - Coord.Dim(18, 'px')
# d is 0.75 inches
d += Coord.Dim(25.4, 'mm')
# d is 1.75 inches
```

Scaling and unit conversion returns a new object:

```
a = Coord.Dim(12, 'px')
b = myObj.scale(6.0)
# b is 72 pixels
c = b.convert('in')
# 1 is 1 inch
```

Comparison:

```
assert (Coord.Dim(1, 'in') == Coord.Dim(72, 'px'))
assert (Coord.Dim(1, 'in') >= Coord.Dim(72, 'px'))
assert (Coord.Dim(1, 'in') <= Coord.Dim(72, 'px'))
assert (Coord.Dim(1, 'in') > Coord.Dim(71, 'px'))
assert (Coord.Dim(1, 'in') < Coord.Dim(73, 'px'))
```

Coord.Pt()

Creation:

```
p = Coord.Pt(
    Coord.Dim(12, 'px'),
    Coord.Dim(24, 'px'),
)
print(p)
# Prints: 'Pt(x=Dim(12px), y=Dim(24px))'
p.x # Coord.Dim(12, 'px')
p.y # Coord.Dim(24, 'px')
# Scale up by 6 and convert units
pIn = p.scale(6).convert('in')
# pIn now 'Pt(x=Dim(1in), y=Dim(2in))'
```

Testing

The unit tests are in test/TestCoord.py.

Plot Pen Stroke

Defines how the stroke of a pen is represented on a plot.

Created on 7 Mar 2011

class TotalDepth.util.plot.Stroke.**Stroke** (*width, colour, coding, opacity*)

Stroke basic properties

coding

Alias for field number 2

colour

Alias for field number 1

opacity

Alias for field number 3

width

Alias for field number 0

TotalDepth.util.plot.Stroke.**StrokeBlackSolid** = **Stroke**(width='1', colour='black', coding=None)

Prototypical black solid stroke Usage: StrokeBlackSolid._replace(width=2.0)

TotalDepth.util.plot.Stroke.**retSVGAttrsFromStroke** (*stroke*)

Returns SVG attributes as a dictionary from a Stroke() object.

SVG Writer Module

An SVG writer.

TODO: Add a float format to reduce the size of the SVG file.

TotalDepth.util.plot.SVGWriter.**DEFAULT_VALUE_FORMAT** = '{:.3f}'

Defaults format for points that are specified in inches or such like

TotalDepth.util.plot.SVGWriter.**DEFAULT_VALUE_FORMAT_POINTS** = '{:.1f}'

Defaults format for points that are specified in pixels

exception TotalDepth.util.plot.SVGWriter.**ExceptionSVGWriter**

Exception class for SVGWriter.

class TotalDepth.util.plot.SVGWriter.**SVGCircle** (*theXmlStream, thePoint, theRadius, attrs=None*)

A circle in SVG. Initialise the circle with a stream, a Coord.Pt() and a Coord.Dim() objects.

See: <http://www.w3.org/TR/2003/REC-SVG11-20030114/shapes.html#CircleElement>

__init__ (*theXmlStream, thePoint, theRadius, attrs=None*)

Initialise the circle with a stream, a Coord.Pt() and a Coord.Dim() objects.

class TotalDepth.util.plot.SVGWriter.**SVGEllipse** (*theXmlStream, ptFrom, theRadX, theRadY, attrs=None*)

An ellipse in SVG. Initialise the circle with a stream, a Coord.Pt() and a Coord.Dim() objects.

See: <http://www.w3.org/TR/2003/REC-SVG11-20030114/shapes.html#EllipseElement>

__init__ (*theXmlStream, ptFrom, theRadX, theRadY, attrs=None*)

Initialise the circle with a stream, a Coord.Pt() and a Coord.Dim() objects.

class TotalDepth.util.plot.SVGWriter.**SVGGroup** (*theXmlStream, attrs=None*)

A group element in SVG.

`__init__` (*theXmlStream*, *attrs=None*)

Initialise the group with a stream.

See: <http://www.w3.org/TR/2003/REC-SVG11-20030114/struct.html#GElement>

Sadly we can't use `**kwargs` because of Python restrictions on keyword names. `stroke-width` is not a valid keyword argument (although `stroke_width` would be). So instead we pass in an optional dictionary `{string : string, ...}`

class `TotalDepth.util.plot.SVGWriter.SVGLine` (*theXmlStream*, *ptFrom*, *ptTo*, *attrs=None*)

A rectangle in SVG. Initialise the line with a stream, and two `Coord.Pt()` objects.

See: <http://www.w3.org/TR/2003/REC-SVG11-20030114/shapes.html#LineElement>

`__init__` (*theXmlStream*, *ptFrom*, *ptTo*, *attrs=None*)

Initialise the line with a stream, and two `Coord.Pt()` objects.

class `TotalDepth.util.plot.SVGWriter.SVGPointList` (*theXmlStream*, *name*, *pointS*, *attrs*)

An abstract class that takes a list of points, derived by polyline and polygon.

Initialise the element with a stream, a name, and a list of `Coord.Pt()` objects.

NOTE: The units of the points are ignored, it is up to the caller to convert them to the User Coordinate System.

TODO: Make the caller supply points as numbers not `Coord.Pt` as this may be faster??? e.g.:

```
FMT_PAIR_STR = FMT_STR + ', ' + FMT_STR
' '.join([self.FMT_PAIR_STR.format(x, y) for x,y in pointS])
```

`__init__` (*theXmlStream*, *name*, *pointS*, *attrs*)

Initialise the element with a stream, a name, and a list of `Coord.Pt()` objects. NOTE: The units of the points are ignored, it is up to the caller to convert them to the User Coordinate System. TODO: Make the caller supply points as numbers not `Coord.Pt` as this may be faster??? e.g. `FMT_PAIR_STR = FMT_STR + ', ' + FMT_STR` `' '.join([self.FMT_PAIR_STR.format(x, y) for x,y in pointS])`

class `TotalDepth.util.plot.SVGWriter.SVGPolygon` (*theXmlStream*, *pointS*, *attrs=None*)

A polygon in SVG. Initialise the polygon with a stream, and a list of `Coord.Pt()` objects.

NOTE: The units of the points are ignored, it is up to the caller to convert them to the User Coordinate System.

See: <http://www.w3.org/TR/2003/REC-SVG11-20030114/shapes.html#PolygonElement>

`__init__` (*theXmlStream*, *pointS*, *attrs=None*)

Initialise the polygon with a stream, and a list of `Coord.Pt()` objects. NOTE: The units of the points are ignored, it is up to the caller to convert them to the User Coordinate System.

class `TotalDepth.util.plot.SVGWriter.SVGPolyline` (*theXmlStream*, *pointS*, *attrs=None*)

A polyline in SVG. Initialise the polyline with a stream, and a list of `Coord.Pt()` objects.

NOTE: The units of the points are ignored, it is up to the caller to convert them to the User Coordinate System.

See: <http://www.w3.org/TR/2003/REC-SVG11-20030114/shapes.html#PolylineElement>

`__init__` (*theXmlStream*, *pointS*, *attrs=None*)

Initialise the polyline with a stream, and a list of `Coord.Pt()` objects. NOTE: The units of the points are ignored, it is up to the caller to convert them to the User Coordinate System.

class `TotalDepth.util.plot.SVGWriter.SVGRect` (*theXmlStream*, *thePoint*, *theBox*, *attrs=None*)

A rectangle in SVG. Initialise the rectangle with a stream, a `Coord.Pt()` and a `Coord.Box()` objects.

See: <http://www.w3.org/TR/2003/REC-SVG11-20030114/shapes.html#RectElement>

Typical attributes:

```
{'fill' : "blue", 'stroke' : "black", 'stroke-width' : "2", }
```

__init__(*theXmlStream, thePoint, theBox, attrs=None*)

Initialise the rectangle with a stream, a Coord.Pt() and a Coord.Box() objects.

See: <http://www.w3.org/TR/2003/REC-SVG11-20030114/shapes.html#RectElement>

Typical attributes:

```
{'fill' : "blue", 'stroke' : "black", 'stroke-width' : "2", }
```

class TotalDepth.util.plot.SVGWriter.SVGText(*theXmlStream, thePoint, theFont, theSize, attrs=None*)

Text in SVG. Initialise the text with a stream, a Coord.Pt() and font as a string and size as an integer. If thePoint is None then no location will be specified (for example for use inside a <defs> element).

See: <http://www.w3.org/TR/2003/REC-SVG11-20030114/text.html#TextElement>

__init__(*theXmlStream, thePoint, theFont, theSize, attrs=None*)

Initialise the text with a stream, a Coord.Pt() and font as a string and size as an integer. If thePoint is None then no location will be specified (for example for use inside a <defs> element).

TotalDepth.util.plot.SVGWriter.dimToText(*theDim*)

Converts a Coord.Dim() object to text for SVG units.

Examples

All these examples assume these imports:

```
import io
from TotalDepth.util import XmlWrite
from TotalDepth.util.plot import SVGWriter
from TotalDepth.util.plot import Coord
```

Construction

Writing to an in-memory file:

```
f = io.StringIO()
vp = Coord.Box(
    Coord.Dim(100, 'mm'),
    Coord.Dim(20, 'mm'),
)
with SVGWriter.SVGWriter(myF, myViewPort):
    pass
print(myF.getvalue())
# Prints:
<?xml version='1.0' encoding="utf-8"?>
<!DOCTYPE svg PUBLIC "-//W3C//DTD SVG 1.1//EN" "http://www.w3.org/Graphics/SVG/1.1/
↪DTD/svg11.dtd">
<svg height="20.000mm" version="1.1" width="100.000mm" xmlns="http://www.w3.org/2000/
↪svg"/>
```

Writing Objects to SVG

Writing a rectangles to a stream:

```
myF = io.StringIO()
vp = Coord.Box(Coord.Dim(5, 'cm'), Coord.Dim(4, 'cm'))
with SVGWriter.SVGWriter(myF, vp) as xS:
    with XmlWrite.Element(xS, 'desc'):
        xS.characters('A couple of rectangles')
    myPt = Coord.Pt(Coord.Dim(0.5, 'cm'), Coord.Dim(0.5, 'cm'))
    myBx = Coord.Box(Coord.Dim(2.0, 'cm'), Coord.Dim(1.0, 'cm'))
    with SVGWriter.SVGRect(xS, myPt, myBx):
        pass
    myPt = Coord.Pt(Coord.Dim(0.01, 'cm'), Coord.Dim(0.01, 'cm'))
    myBx = Coord.Box(Coord.Dim(4.98, 'cm'), Coord.Dim(3.98, 'cm'))
    with SVGWriter.SVGRect(xS, myPt, myBx, attrs= {'fill' : "none", 'stroke' : "blue",
↪ 'stroke-width' : ".02cm"}):
        pass
print(myF.getvalue())
# Prints:
<?xml version='1.0' encoding="utf-8"?>
<!DOCTYPE svg PUBLIC "-//W3C//DTD SVG 1.1//EN" "http://www.w3.org/Graphics/SVG/1.1/
↪DTD/svg11.dtd">
<svg height="4.000cm" version="1.1" width="5.000cm" xmlns="http://www.w3.org/2000/svg
↪">
    <desc>A couple of rectangles</desc>
    <rect height="1.000cm" width="2.000cm" x="0.500cm" y="0.500cm"/>
    <rect fill="none" height="3.980cm" stroke="blue" stroke-width=".02cm" width="4.
↪980cm" x="0.010cm" y="0.010cm"/>
</svg>
```

Plot Constants for Wireline Logs

Some basic constants used in plotting.

Created on Jan 5, 2012

```
TotalDepth.util.plot.PlotConstants.DEFAULT_PLOT_UNITS = 'in'
    Default SVG plot units
```

```
TotalDepth.util.plot.PlotConstants.DEFAULT_PLOT_LIS_UNITS = b'IN '
    Units that we can convert to in LIS terms
```

```
TotalDepth.util.plot.PlotConstants.VIEW_BOX_UNITS_PER_PLOT_UNITS = 96.0
    Number of pixels per standard plot unit
```

```
TotalDepth.util.plot.PlotConstants.MarginQtrInch = Margin(left=Dim(value=0.25, units='in'),
    Definition of a quarter inch margin
```

```
TotalDepth.util.plot.PlotConstants.STANDARD_PAPER_WIDTH = Dim(value=8.5, units='in')
    Standard wireline log fan paper width i.e. long side.
```

```
TotalDepth.util.plot.PlotConstants.STANDARD_PAPER_DEPTH = Dim(value=6.25, units='in')
    Standard wireline log fan paper depth i.e. short side.
```

```
TotalDepth.util.plot.PlotConstants.STANDARD_PAPER_MARGIN = Margin(left=Dim(value=0.25, units='in'),
    Standard wireline log fan paper margin.
```

Track Module

Created on 28 Feb 2011

Plotting LIS data requires these components: * A PlotConfig object * A data set (e.g. a LogPass with a FrameSet). * An output driver (e.g. screen, print PDF, web SVG).

User creates a PlotConfig (this reflects a PRES table). This is reusable.

User specifies a data set (from, to, channels etc.). e.g. `Invoke LogPass.setFrameSet(File, theFrameSlice=theFrameSlice, theChList=theChList)`

User says ‘plot this data set with this configuration to this output device’. e.g. `Plot(PlotConfig, LogPass, PlotDevice)` Plot uses `LogPass.frameSet.genChScValues(ch, sc)` to plot individual curves.

Lacunae

Area plotting. Caching (e.g. SVG fragments - is this worth it?)

PlotConfig

PlotTracks

Typically a three track (+depth) have these dimensions in inches:

| Track | Left | Right | Width |
|-------|------|-------|-------|
| 1 | 0 | 2.4 | 2.4 |
| Depth | 2.4 | 3.2 | 0.8 |
| 2 | 3.2 | 5.6 | 2.4 |
| 3 | 5.6 | 8.0 | 2.4 |

Track names can be split (e.g. LHT1 is left hand track 1) or merged (T23 is spread across tracks two and three).

Examples of PRES and FILM records:

| Table record (type 34) type: PRES | | | | | | | | | |
|-----------------------------------|------|------|------|------|------|------|----------|----------|---------|
| MNEM | OUTP | STAT | TRAC | CODI | DEST | MODE | FILT | LEDG | REDG |
| ----- | | | | | | | | | |
| SP | SP | ALLO | T1 | LLIN | 1 | SHIF | 0.500000 | -80.0000 | 20.0000 |
| CALI | CALI | ALLO | T1 | LDAS | 1 | SHIF | 0.500000 | 5.00000 | 15.0000 |
| MINV | MINV | DISA | T1 | LLIN | 1 | SHIF | 0.500000 | 30.0000 | 0.00000 |
| MNOR | MNOR | DISA | T1 | LDAS | 1 | SHIF | 0.500000 | 30.0000 | 0.00000 |
| LLD | LLD | ALLO | T23 | LDAS | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| LLDB | LLD | ALLO | T2 | HDAS | 1 | GRAD | 0.500000 | 2000.00 | 200000. |
| LLG | LLG | DISA | T23 | LDAS | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| LLGB | LLG | DISA | T2 | HDAS | 1 | GRAD | 0.500000 | 2000.00 | 200000. |
| LLS | LLS | ALLO | T23 | LSPO | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| LLSB | LLS | ALLO | T2 | HSPO | 1 | GRAD | 0.500000 | 2000.00 | 200000. |
| MSFL | MSFL | ALLO | T23 | LLIN | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| Table record (type 34) type: FILM | | | | | | | | | |
| MNEM | GCOD | GDEC | DEST | DSCA | | | | | |
| ----- | | | | | | | | | |

```

1      E20   -4--  PF1   D200
2      EEE   ----  PF2   D200

```

Table record (type 34) type: PRES

| MNEM | OUTP | STAT | TRAC | CODI | DEST | MODE | FILT | LEDG | REDG |
|------|------|------|------|------|------|------|----------|-----------|-----------|
| NPHI | NPHI | ALLO | T23 | LDAS | 1 | SHIF | 0.500000 | 0.450000 | -0.150000 |
| DRHO | DRHO | ALLO | T3 | LSPO | 1 | NB | 0.500000 | -0.250000 | 0.250000 |
| PEF | PEF | ALLO | T23 | LGAP | 1 | SHIF | 0.500000 | 0.00000 | 10.0000 |
| SGR | | DISA | T1 | LLIN | 1 | SHIF | 0.500000 | 0.00000 | 300.000 |
| CGR | | DISA | T1 | LGAP | 1 | SHIF | 0.500000 | 0.00000 | 300.000 |
| TENS | TENS | DISA | T3 | LGAP | 1 | SHIF | 0.500000 | 14000.0 | 4000.00 |
| CAL | CALI | ALLO | T1 | LSPO | 1 | SHIF | 0.500000 | 5.00000 | 15.0000 |
| BS | BS | DISA | T1 | LGAP | 1 | SHIF | 0.500000 | 5.00000 | 15.0000 |
| FFLS | FFLS | DISA | T1 | LLIN | 2 | NB | 0.500000 | -0.150000 | 0.150000 |
| FFSS | FFSS | DISA | T1 | LDAS | 2 | NB | 0.500000 | -0.150000 | 0.150000 |
| LSHV | LSHV | DISA | T3 | LLIN | 2 | WRAP | 0.500000 | 2150.00 | 2250.00 |
| SSHV | SSHV | DISA | T3 | LDAS | 2 | WRAP | 0.500000 | 1950.00 | 2050.00 |
| FLS | FLS | DISA | T2 | LLIN | 2 | SHIF | 0.500000 | 0.00000 | 150.000 |
| FSS | FSS | DISA | T2 | LDAS | 2 | SHIF | 0.500000 | 0.00000 | 150.000 |
| RHOB | RHOB | ALLO | T23 | LLIN | 1 | SHIF | 0.500000 | 1.95000 | 2.95000 |
| PHIX | PHIX | ALLO | T1 | LLIN | 1 | NB | 0.500000 | 0.500000 | 0.00000 |

Table record (type 34) type: FILM

| MNEM | GCOD | GDEC | DEST | DSCA |
|------|------|------|------|------|
| 1 | EEE | ---- | PF2 | D200 |
| 2 | EEE | ---- | PF1 | DM |

Other FILM Table Examples:

Table record (type 34) type: FILM

| MNEM | GCOD | GDEC | DEST | DSCA |
|------|------|------|------|------|
| 1 | EEB | ---- | PF1 | D200 |
| 2 | EEB | ---- | PF2 | DM |

Table record (type 34) type: FILM

| MNEM | GCOD | GDEC | DEST | DSCA |
|------|------|------|------|------|
| 1 | E20 | -4-- | PF1 | D200 |
| 2 | EEE | ---- | PF2 | D200 |

| MNEM | GCOD | GDEC | DEST | DSCA |
|------|------|------|------|------|
| 1 | EEE | ---- | PF1 | D200 |
| 2 | E1E | -4- | PF2 | D200 |

Table record (type 34) type: FILM

| MNEM | GCOD | GDEC | DEST | DSCA |
|------|------|------|------|------|
|------|------|------|------|------|

```

-----
D      E3E  -3-  PFD  D200
E      E3E  -3-  PFE  D500
5      EB0   ---  PF5  D200
6      EEB   ---  PF6  D200

Table record (type 34) type: FILM

MNEM  GCOD  GDEC  DEST  DSCA
-----

8      EB0   ---  PF8  D200
A      LLLL  1111  PFA  DM
E      E4E  -4-  PFE  D200
K      E4E  -4-  PFK  D500

Table record (type 34) type: FILM

MNEM      CINT      GCOD  GDEC  DEST  DSCA
-----

1          0.00000  E2E   -2-  PF1   D200
2          0.00000  E2E   -1-  PF2   D500
3          0.00000  EEE   ----  NEIT   S5
4          0.00000  EEE   ----  NEIT   S5

Table record (type 34) type: FILM

MNEM      CINT      GCOD  GDEC  DEST  DSCA
-----

1          300.000  E2E   -2-  PF1   D200
2          300.000  E2E   -2-  PF2   D500
3          300.000  EEE   ----  NEIT   S5
4          300.000  EEE   ----  NEIT   S5

Table record (type 34) type: FILM

MNEM      CINT      GCOD  GDEC  DEST  DSCA
-----

1          50.0000  EEE   ----  PF1   D200
2          0.00000  EEE   ----  PF2   D200
3          0.00000  EEE   ----  NEIT   D200
4          0.00000  EEE   ----  NEIT   D200

```

Minimal, but not complete interpretation:

```

Ignore GDEC as dupe.
E - Equi-spaced (linear).
n - Log with number of decades.
B - Blank.
L - ?

```

What to do with 0 (continuation?). Examples: E20 -4- means 4 decades over track 23.

exception TotalDepth.util.plot.Track.ExceptionTotalDepthLISPlotTrack

Exception for plotting tracks.

`TotalDepth.util.plot.Track.genLinear10(l, r)`

Generate a linear series of 10 track grid lines as (Stroke, position).

`TotalDepth.util.plot.Track.genLog10(l, r, cycles=1, start=1)`

Generate a log10 series of track grid lines as (Stroke, position). cycles is the number of log cycles to split the track up into. start is the start position of the scale e.g. 2 for common resistivity curves. So cycles=2, start=2 would give log grid 2 to 20000 i.e. to plot resistivity in the range 0.2 to 2000.

`TotalDepth.util.plot.Track.genLog10Decade2 = functools.partial(<function genLog10>, cycles=2)`

Generator for 2 decades of log base 10

`TotalDepth.util.plot.Track.genLog10Decade3 = functools.partial(<function genLog10>, cycles=3)`

Generator for 3 decades of log base 10

`TotalDepth.util.plot.Track.genLog10Decade4 = functools.partial(<function genLog10>, cycles=4)`

Generator for 4 decades of log base 10

`TotalDepth.util.plot.Track.genLog10Decade5 = functools.partial(<function genLog10>, cycles=5)`

Generator for 5 decades of log base 10

`TotalDepth.util.plot.Track.genLog10Decade1Start2 = functools.partial(<function genLog10>, cycles=1, start=2)`

Generator for 1 decade of log base 10 starting at 2

`TotalDepth.util.plot.Track.genLog10Decade2Start2 = functools.partial(<function genLog10>, cycles=2, start=2)`

Generator for 2 decades of log base 10 starting at 2

class `TotalDepth.util.plot.Track.Track(leftPos, rightPos, gridGn, plotXLines=True, plotXAlpha=0.5, plotYLines=True, plotYAlpha=0.5, DEPTH_PER_CH=0.25, units='in')`

Class that represents a single track. The track, as a structural graphical element, is merely a grid. The actual curves are plotted on panes that are independent from a single track (can span multiple tracks for example).

`leftPos` - A `Coord.Dim()` object that is the left edge.

`rightPos` - A `Coord.Dim()` object that is the right edge.

`gridGn` - A generator of line positions, None for blank track.

`plotXLines` - If True then plot X Axis information (depth lines) in this track.

`plotXAlpha` - If True then plot X Axis information (depth numbers) in this track.

DEPTH_PER_CH = `Dim(value=0.25, units='in')`

Space for plotting the scale for each curve

left

The left edge as a `Coord.Dim()`.

right

The right edge as a `Coord.Dim()`.

hasGrid

True if there is a grid to be generated for this track.

plotSVG (*topLeft*, *depth*, *theSVGWriter*)

Plot the track gridlines. `topLeft` - A `Coord.Pt()` object that is the top left of the canvas. `depth` - A `Coord.Dim()` object that is the total depth of the grid below `topLeft`. `drive` - The plot driver.

X Axis Grid Line Module

Provides plotting support for the X axis grid i.e. Depth grid lines and text.

Created on 28 Feb 2011

TODO: Remove APIs that are not used by Plot or anything. Plot only appears to use `genXAxisRange()` and `genXAxisTextRange()`.

exception `TotalDepth.util.plot.XGrid.ExceptionPlotXGrid`
Exception for plotting.

`TotalDepth.util.plot.XGrid.StrokeGreySolid = Stroke(width='1', colour='grey', coding=None,`
Definition of a grey solid stroke Usage: `StrokeBlackGrey._replace(width=2.0)`

class `TotalDepth.util.plot.XGrid.XGrid(scale)`
Class that can generate depth line grid and alphanumeric values. Constructed with integer scale.

DEFAULT_INTERVAL_MAP = {1: `Stroke(width=0.5, colour='black', coding=None, opacity=1.0`
Default for unknown units and scale, this is basically like simple graph paper

DEFAULT_INTERVAL_TEXT = 100
Default position for text on the X axis

__init__ (*scale*)
Constructor with integer scale. We make scale a constructor argument as we know that up front. We don't necessarily know the X units.

genXAxisRange (*evFrom, evTo*)
Generates a bounded series of X axis line plot positions as (`Dim()`, `Stroke()`). *evFrom* and *evTo* and `EngVal` objects.

genXPosStroke (*xFrom, xInc, units*)
Generates unbounded series of X line positions as (`Dim()`, `Stroke()`).

xFrom - The starting value as a float, positions may not include this if fractional. First x position generated will be `math.ceil()` if *xInc*, `math.floor()` otherwise.

xInc - A boolean, True if X increases.

units - Units of X axis e.g. b'FEET'.

genEventsUnits (*xFrom, xInc, units*)
Generates events from/to in units.

genXAxisTextRange (*evFrom, evTo*)
Generates a bounded series of X axis line plot positions as (`Dim()`, `value`). *evFrom* and *evTo* and `EngVal` objects.

__weakref__
list of weak references to the object (if defined)

XML Plot Description Low-level support

Provides low level support for XML plot configurations

Created on Dec 13, 2011

exception `TotalDepth.util.plot.XMLCfg.ExceptionXMLCfg`
Exception class for this module.

exception `TotalDepth.util.plot.XMLCfg.ExceptionXMLCfgWrongRootElem`
Exception when the root element is wrong.

exception `TotalDepth.util.plot.XMLCfg.ExceptionXMLCfgMissingElem`
Exception when there is a missing mandatory element.

exception TotalDepth.util.plot.XMLCfg.**ExceptionXMLCfgNoContent**
Exception when the is missing content.

class TotalDepth.util.plot.XMLCfg.LgXMLBase
Base class for XML functionality that can be used by both FILM and PRES XML classes.

str (*e*, *name*, *default=None*)
Returns the text in a single child element or None.

bool (*e, name, default=False*)
Returns the text in a single child element converting 1/0 to True/False.

int (*e, name, default=0*)
Returns the text in a single child element as an integer defaulting to 0.

float (*e, name, default=0.0*)
Returns the text in a single child element as a float.

XML Plot Description Discovery

This looks at the available XML LgFormats and works out what curves of a LogPass or LASFile can be plotted by each one.

Created on Jan 21, 2012

`TotalDepth.util.plot.XMLMatches.fileCurveMap` (*theLpOrLasFile*, *directory=None*)
Returns a map of {FilmID : [OUTP, ...], ...} which is a list of OUTP in theLpOrLasFile that could be plotted with that film ID.

`TotalDepth.util.plot.XMLMatches.fileCurveMapFromFILM` (*theLpOrLasFile*, *theFilmCfg*)
Returns a map of {FilmID : [OUTP, ...], ...} which is a list of OUTP in theLpOrLasFile that could be plotted with that film ID.

AREA Plotting Configuration

Module for plotting areas of particular patterns wirth well log data.

Created on 1 Apr 2011

Note on patterns in XML file in: `formats\IWWPatterns.xml`

There are elements thus:

```
<Bits>/+7/7v/u/+7/7gAA7/7v/u/+7/7v/gAA</Bits>  
<PatternHeight>12</PatternHeight>  
<PatternWidth>15</PatternWidth>
```

Frequency analysis shows that the characters used are '+', '/', A-Z, a-z, 0-9 so this looks like base64 encoded. Length is always 32 chars (256 bits). Pattern size suggests $12 \times 15 = 180$ bits.

Examples:

```
>>> base64.b64decode(b'/' + 77v/u/+77gAA77v/u/+77v/gAA')
b'ÿïÿïÿïÿïî\\ïpïpïpïpïp\\'

<Description>Coal-LigNite</Description>
>>> base64.b64decode(b'AAAAAAAAAAAAAAAAAAAAAAAAAAAAA')
b'////////////////////////////////////////'
```

Length is always 24 bytes (192 bits) 12x16 ? This looks promising:

```
>>> l = list(b'Ø|ß¹îv|ï²ÝÎÚ~»f|ÝÕæ&')
>>> s = ['{:08b}'.format(v) for v in l]
```

Or shortened:

```
st = ''.join(['{:08b}'.format(v) for v in b'...'])
print('\n'.join([st[i:i+12] for i in range(16)]))
```

Hmmm 12 zeros, perhaps it is 12x15 after all:

```
>>> base64.b64decode(b' /+7/7v/u/+7/7gAA7/7v/u/+7/7v/gAA')
b'ÿÿÿÿÿÿÿÿÿ\\ïþïþïþïþ\\'
```

Full range (sorted):

```
//4zAP/6//oA9v+//4zAP/8//oA+v/2
//6/AIP+//4Avv+C//6/AIP+//4Avv+C
//60ks+//6ZaP+e//60ks+//6ZaP+e
//69fIEA//4QENfW//69fIEA//4QENf2
//6N5r/mj76/urm+ub7v8u7+774t8v/y
//6v1vt+rOr//lq2/87//rrq//7XXu++
//7//v+//7//v+//7//v+//7//v/+
//7/3t/e397fwsP+//7/3t/e397fwsP+
//7/AP+//4A/v+//7/AP+//4A/v/+
//7/AP+/+9YA7v/W1/7vANf+/9YA7v/W
//7/AP/+Wv4A/v+//7/AP/+Wv4A/v/+
//7/APv+9/4A/v/6//b/AP3+8/4A/v/+
//73/uv+wf7//v+//7/3v+u/wb//v/+
//732gAAvfbvfAAAu97vegAAve73fAAA
//7bAP+//4A1v+//7bAP+//4A1v/+
//7bAPv+9/4A1v/6//bbAP3+8/4A2v/+
//7HHoLugu7HHv+//6PxneCd4KPxv/+
//7HHrruuu7HHv+//6Pxne6d7qPxv/+
//7nAP+/+4A7v/u//7nAP+/+4A7v/u
//7nO0c4//45z jnO//7nO0c4//45z jnO
//7nO0c4//45zv/O//7nOP8+//45zvn+
//7vAP+//4A7v+//7vAP+//4A7v/+
//b/9v/2+7b5Ngqg+777vv/+9/73/gAA
//b/9v/2+7b7tgqg+T77vv/+9/73/gAA
//b/9v/2+Db79gog+774Pv/+9/73/gAA
//b/9v/2+Hb7tghg+774fv/+9/73/gAA
//b/9v/2+Pb7dgjA+//77/v/+9/73/gAA
/+4zLv/uzOj/7gcA3/7TMt/+XMzf/gBy
/+6B7n7uge7/7gAA7/7vAu787wLv/gAA
/+7/7rvux+7/7gAA7/7v/u+678bv/gAA
/+7/7sHu/+7/7gAA797vvu/+7/7v/gAA
/+7/7uDv/+7/7gAA7/7v/u8G7/7v/gAA
/+7/7v/u/+7/7gAA7/7v/u/+7/7v/gAA
/+7/7v/u/+7/7oOC7/7v/u/+7/7v/oOC
/+7/7v/u/+7bbAAA7/7v/u/+7/5ttgAA
/+7/7v/u/+r/5gAA7/7v/u/+6/7n/gAA
/+7/7vPu/+7/7gAA7/7v/u8+7/7v/gAA
```

```

/+7/7vPu/+7/7gAA7/7v/u8G7/7v/gAA
/+7/7vPu/+7/7gAA797vvu/+7/7v/gAA
/+7/AP/+7/4A/v/+7/AP/+7/4A/v/+
/+717vvu9e7/7gAA7/7vlu/u79bv/gAA
/+73xuPG44LB/v/+73xuPG44LB/v/+
/+7bAP/+7/4A1v/+7bAP/+7/4A1v/+
/+7n7oHu5+7/7gAA7/7vzu8C787v/gAA
/+7v7sfu7+7/7gAA7/7v7u/G7+7v/gAA
/+7v7tfu7+7/7gAA7/7v7u/W7+7v/gAA
/+7vAP/+7/4A7v/+7vAP/+7/4A7v/+
/+7X7oPu1+7/7gAA7/7vlu+C79bv/gAA
/+bP2ofah+bP/v8+/h7+Hs8+t/63/s/+
/+bP2rfat+bP/v8+/t7+3s8+t/63/s/+
/34a4Pn+AAD/+sHW/84AAO/+Xg4//gAA
/34ekP3+AAD/+gc2/+4AAO/+3MC//gAA
/34O4P3+AAD/+uD2/+4AAO/+3wa//gAA
/36a8vn+AAD/+ufW/84AAO/+Xz4//gAA
/37+/v3+AAD/+v/2/+4AAO/+3/6//gAA
/376/vn+AAD/+v/W/84AAO/+X/4//gAA
/37Ozv3+AAD/+s/2/+4AAO/+356//gAA
/3b/jv+u/47/dv/+u/7H/tf+x/67/v/+
/97/wP/e+N77Xvje+/77/v/g//4AHv/+
/d773vvuAAC+/r7+f34AAPfu7/bv9gAA
/wKBer0Cgf7//v/+7/AoF6vQKB/v/+
+/73MgH//Yz7v4C+/73MgP//Yz7v4C
2/7nMu/+3/75mP/+7Yzzv/e/76Z8v/+
2Hzfkrnudnzvst3O2n67gmZ83Z7V5iYa
3/4HMv/+4zgV/+3/4HMv/+4zgV/+
3/6s+N/+451v/u3/6s+N/+451v/u
3d7u7vd2e7q93N7u73b3unvcve7e9u96
3d7urvZ2ebq53Nbqz3a3inucvW7e9u16
3dz//v/+d3b//v/+3dz//v/+d3b//v/+
4er//tde//764P/+117//uHq//7XXv/+
4er//td0//764P/+117f/sHq//7XXv/+
5/6BAOf/+aAgP/m5/6BAOf/+aAgP/m
5+aB/uf+/87/Ao/OvH6lfrT+hX7/5v+A
5mb//szm//6ZmP//4zOP//45zv/+
5zL//pnO//7nMv/+mc7//ucy//45zv/+
7/6rMu/+AADu7qqq7u4AAP7uMqr+7gAA
7/7vAO/+4A7v/u7/7vAO/+4A7v/u
8e7u7u7u7u7x7gAA7x7u7u7u7vHgAA
9/7nANf//YA5v/W9/7nANf//YA5v/W
9/7nMt f/+4zzv+u9/7nMt f/+4zzv+u
9/7vAN//YA7v/e9/7vAN//YA7v/e
9fT//l9e//719P/+X17//vX0//5fXv/+
AAAAAAAAAAAAAAAAAAAAAAAAAAAA
AAD//gAA//4AAP/+AAD//gAA//4AAP/+
ff67/td877r/1v/uff67/td877r/1v/u
JJK22pJIJJK22pJIJJK22pJIJJK22pJI
m/73Mu//bM7v/eO/73Mu//aZ7v/e
MzL//szO//6DwP/+zM7//v/+ODj//s/O
u/7WeO//7o81v/uu/7WeO//7r/1jzu
u/7WeO//7o81v/uu/7WeO//7r/1rvu
u/7XAO//7oA1v/uu/7XAO//7oA1v/u
uur//tdc//666v/+11z//rrq//7XXP/+
w+6Z7mbuWu7/7gAA74bvMu7M7rTv/gAA
x+677qvuu+7H7gAA78bvuu+q77rvxgAA
z/4DMs//84zAv/Oz/4DMs//84zAv/O

```

```
zM7MzszOzM7MzszOzM7MzszOzM7MzszO
zv4/PvnOx/I+/P9+/b7z3s/uvfb+fvu+
```

```
TotalDepth.util.plot.AREACfg.PATTERN_MAP = {'Void': b'//7//v/+//7//v/+//7//v/+//7//v/+',
        A map of {pattern name : bytes, ...}
```

```
TotalDepth.util.plot.AREACfg.pprintPattern(theName)
    Pretty print the pattern.
```

```
TotalDepth.util.plot.AREACfg.pprintAll()
    Pretty print all patterns.
```

FILM Plotting Configuration

Represents the part of a plot configuration that, typically, can be obtained from a LIS FILM table.

Created on 21 Mar 2011

Example of the data in a film table:

```
Table record (type 34) type: FILM
```

| MNEM | GCOD | GDEC | DEST | DSCA |
|------|------|------|------|------|
| 1 | EEE | ---- | PF2 | D200 |
| 2 | EEE | ---- | PF1 | DM |

Other FILM Table Examples:

```
Table record (type 34) type: FILM
```

| MNEM | GCOD | GDEC | DEST | DSCA |
|------|------|------|------|------|
| 1 | EEB | ---- | PF1 | D200 |
| 2 | EEB | ---- | PF2 | DM |

```
Table record (type 34) type: FILM
```

| MNEM | GCOD | GDEC | DEST | DSCA |
|------|------|------|------|------|
| 1 | E20 | -4-- | PF1 | D200 |
| 2 | EEE | ---- | PF2 | D200 |

| MNEM | GCOD | GDEC | DEST | DSCA |
|------|------|------|------|------|
| 1 | EEE | ---- | PF1 | D200 |
| 2 | E1E | -4- | PF2 | D200 |

```
Table record (type 34) type: FILM
```

| MNEM | GCOD | GDEC | DEST | DSCA |
|------|------|------|------|------|
| D | E3E | -3- | PFD | D200 |
| E | E3E | -3- | PFE | D500 |
| 5 | EB0 | --- | PF5 | D200 |
| 6 | EEB | --- | PF6 | D200 |

Table record (type 34) type: FILM

| MNEM | GCOD | GDEC | DEST | DSCA |
|-------|------|------|------|------|
| ----- | | | | |
| 8 | EB0 | --- | PF8 | D200 |
| A | LLLL | 1111 | PFA | DM |
| E | E4E | -4- | PFE | D200 |
| K | E4E | -4- | PFK | D500 |

Table record (type 34) type: FILM

| MNEM | CINT | GCOD | GDEC | DEST | DSCA |
|-------|---------|------|------|------|------|
| ----- | | | | | |
| 1 | 0.00000 | E2E | -2- | PF1 | D200 |
| 2 | 0.00000 | E2E | -1- | PF2 | D500 |
| 3 | 0.00000 | EEE | ---- | NEIT | S5 |
| 4 | 0.00000 | EEE | ---- | NEIT | S5 |

Table record (type 34) type: FILM

| MNEM | CINT | GCOD | GDEC | DEST | DSCA |
|-------|---------|------|------|------|------|
| ----- | | | | | |
| 1 | 300.000 | E2E | -2- | PF1 | D200 |
| 2 | 300.000 | E2E | -2- | PF2 | D500 |
| 3 | 300.000 | EEE | ---- | NEIT | S5 |
| 4 | 300.000 | EEE | ---- | NEIT | S5 |

Table record (type 34) type: FILM

| MNEM | CINT | GCOD | GDEC | DEST | DSCA |
|-------|---------|------|------|------|------|
| ----- | | | | | |
| 1 | 50.0000 | EEE | ---- | PF1 | D200 |
| 2 | 0.00000 | EEE | ---- | PF2 | D200 |
| 3 | 0.00000 | EEE | ---- | NEIT | D200 |
| 4 | 0.00000 | EEE | ---- | NEIT | D200 |

Minimal, but not complete interpretation:

Ignore GDEC as dupe.

- E - Equi-spaced (linear).
- n - Log with number of decades.
- B - Blank.
- L - ?

What to do with 0 (continuation?). Examples: E20 -4- means 4 decades over track 23.

Four tracks, from 200099.S07:

Table record (type 34) type: FILM

| MNEM | GCOD | GDEC | DEST | DSCA |
|-------|------|------|------|------|
| ----- | | | | |


```
2011-05-27 09:23:24,649 ERROR    Can not read LIS file ../../pLogicTestData/LIS/
↳13610.S1 with error: Can not fit integer number of frames length 7176 into LR
↳length 13354, modulo 6178 [indirect size 0].
...
```

GCOD:

```
===== Count of all table entries =====
{
"(34, b'FILM', b'GCOD', b'BBB ')": 2,
"(34, b'FILM', b'GCOD', b'E1E ')": 5,
"(34, b'FILM', b'GCOD', b'E20 ')": 26,
"(34, b'FILM', b'GCOD', b'E2E ')": 40,
"(34, b'FILM', b'GCOD', b'E3E ')": 3,
"(34, b'FILM', b'GCOD', b'E40 ')": 2,
"(34, b'FILM', b'GCOD', b'E4E ')": 3,
"(34, b'FILM', b'GCOD', b'EB0 ')": 2,
"(34, b'FILM', b'GCOD', b'EEB ')": 22,
"(34, b'FILM', b'GCOD', b'EEE ')": 225,
"(34, b'FILM', b'GCOD', b'LLLL')": 1,
}
===== Count of all table entries END =====
```

GDEC:

```
===== Count of all table entries =====
{
"(34, b'FILM', b'GDEC', b'--- ')": 10,
"(34, b'FILM', b'GDEC', b'----')": 227,
"(34, b'FILM', b'GDEC', b'-1- ')": 2,
"(34, b'FILM', b'GDEC', b'-2- ')": 6,
"(34, b'FILM', b'GDEC', b'-2--')": 32,
"(34, b'FILM', b'GDEC', b'-3- ')": 3,
"(34, b'FILM', b'GDEC', b'-4- ')": 10,
"(34, b'FILM', b'GDEC', b'-4--')": 26,
"(34, b'FILM', b'GDEC', b'1111')": 1,
"(34, b'FILM', b'GDEC', b'EEE ')": 14,
}
===== Count of all table entries END =====
```

DEST:

```
===== Count of all table entries =====
{
"(34, b'FILM', b'DEST', b'NEIT')": 66,
"(34, b'FILM', b'DEST', b'PF1 ')": 124,
"(34, b'FILM', b'DEST', b'PF2 ')": 125,
"(34, b'FILM', b'DEST', b'PF5 ')": 1,
"(34, b'FILM', b'DEST', b'PF6 ')": 5,
"(34, b'FILM', b'DEST', b'PF8 ')": 1,
"(34, b'FILM', b'DEST', b'PFA ')": 1,
"(34, b'FILM', b'DEST', b'PFD ')": 2,
"(34, b'FILM', b'DEST', b'PFE ')": 3,
"(34, b'FILM', b'DEST', b'PFJ ')": 2,
"(34, b'FILM', b'DEST', b'PFK ')": 1,
}
===== Count of all table entries END =====
```

DSCA:

```
===== Count of all table entries =====
{
"(34, b'FILM', b'DSCA', b'D200')": 156,
"(34, b'FILM', b'DSCA', b'D500')": 17,
"(34, b'FILM', b'DSCA', b'DM  ')": 76,
"(34, b'FILM', b'DSCA', b'S5  ')": 82,
}
===== Count of all table entries END =====
```

exception TotalDepth.util.plot.FILMCfg.ExceptionFILMCfg
Specialisation of exception for this module.

exception TotalDepth.util.plot.FILMCfg.ExceptionPhysFilmCfg
Specialisation of exception for PhysFilmCfg.

exception TotalDepth.util.plot.FILMCfg.ExceptionFilmCfgLISRead
Specialisation of exception for FilmCfgLISRead in this module.

class TotalDepth.util.plot.FILMCfg.PhysFilmCfg(*theName, theTracks, theDest, theX*)
Contains the configuration equivalent to a single line in a FILM table.

theName is a hashable.

theTracks is a list of Track.Track objects.

theX is an integer scale.

__init__(*theName, theTracks, theDest, theX*)

Constructor. theName is a hashable. theTracks is a list of Track.Track objects. theX is an integer scale.

name

Name of the FILM.

xScale

The FILM X axis scale as a number.

__len__()

Number of Track.Track objects.

__getitem__(*i*)

Returns the Track.Track object at position i.

genTracks()

Generate all tracks.

interpretTrac(*theTracStr*)

Turns TRAC information into left/right positions as Coord.Dim() objects and the number of half-tracks of the start and half-tracks covered. The later two values are used for stacking and packing the plot header and footer scales so that they take the minimum space.

e.g. b'T23 ' returns: (the left position of T2, right of T3, 4, 4).

e.g. b'T2 ' returns: (the left position of T2, right of T2, 4, 2).

Note: There is some fudging going on here

__weakref__

list of weak references to the object (if defined)

class TotalDepth.util.plot.FILMCfg.PhysFilmCfgLISRead(*theRow*)

Tracks from a LIS FILM table, essentially the pair of GCOD and GDEC defines the left-to-right layout of the plot.

Grid codes from analysis above: b'BBB ', b'E1E ', b'E20 ', b'E2E ', b'E3E ', b'E40 ', b'E4E ', b'EB0 ', b'EEB ', b'EEE ', b'LLLL'

The DSCA defines the top-to-bottom nature of the plot. DSCA codes from analysis above: b'D200', b'D500', b'DM ', b'S5 '

But we can guess some others...

```
DSCA_MAP = {b'D20 ': 20, b'D40 ': 40, b'D200': 200, b'D240 ': 240, b'D500': 500, b'D540 ': 540, b'DM ': 1000, b'S5 ': 1000}
X axis scale from a LIS FILM table DSCA codes from analysis above: b'D200', b'D500', b'DM ', b'S5 '
But we can guess some others...
```

__init__ (*theRow*)

Reads a LogiRec.TableRow object and populates a CurveCfg.

Example:

| MNEM | GCOD | GDEC | DEST | DSCA |
|------|------|------|------|------|
| 1 | E20 | -4-- | PF1 | D200 |

supportedFilmTracks ()

A list of supported film (name, decade) pairs.

class TotalDepth.util.plot.FILMCfg.FilmCfg

Contains the configuration equivalent to a complete FILM table.

add (*k, thePfc*)

Add a PhysFilmCfg object to the map with key *k*, typically a FILM mnemonic in bytes such as Mnem.Mnem(b'1 ') or some other ID such as a string, the filename of an XML file.

keys ()

All FILM Mnemonics.

__len__ ()

Number of unique film destination names.

__getitem__ (*name*)

Returns the PhysFilmCfg object corresponding to *name* - a Mnem() object. Will raise KeyError if not exact match. See retFilmDest() for an API that can handle curve destinations of BOTH, ALL etc.

__contains__ (*name*)

Membership test.

retAllFILMDests (*curveDestID*)

Returns an unordered list of FILM destinations for a curve destination. For example if curveDestID is b'BOTH' this might return [b'2 ', b'1 ']

retFILMDest (*filmDestID, curveDestID*)

Returns a PhysFilmCfg object by matching curveDestID to the filmDestID. Returns None on failure. For LIS curveDestID can be 1, BOTH, ALL, NEIT etc. This is commonly used by the PRESCfg module so that interpretTrac() can be called on the result and thus build up a map of track positions for all possible logical film outputs.

interpretTrac (*filmDestID, curveDestID, trackStr*)

Given a film destination ID and a curve destination (which could be b'ALL') and a track string (e.g. b'T23') this returns the left/right positions as Coord.Dim() objects and the number of half-tracks of the start and half-tracks covered (used for plot header and footer scales). Returns None if there is no match for the filmDestID/curveDestID (for example if curveDestID is b'NEIT'). e.g. (b'1 ', b'BOTH', b'T23 ') returns: (the left position of T2, right of T3, 4, 4).

__weakref__

list of weak references to the object (if defined)

class TotalDepth.util.plot.FILMCfg.FilmCfgLISRead(*theLr*)

Interprets a FILM table from a LIS Logical Record.

__init__(*theLr*)

Reads a LogiRec.Table object and creates a PhysFilmCfgLISRead for each row.

Typical FILM table:

| MNEM | GCOD | GDEC | DEST | DSCA |
|-------|------|------|------|------|
| ----- | | | | |
| 1 | E20 | -4-- | PF1 | D200 |
| 2 | EEE | ---- | PF2 | D200 |

retAllFILMDestS(*curveDestID*)

Returns an unordered list of FILM destinations for a curve destination.

For example if curveDestID is b'BOTH' this might return [b'2 ', b'1 ']

retFILMDest(*filmDestID*, *curveDestID*)

Returns a PhysFilmCfg object by matching curveDestID to the filmDestID. Returns None on failure. curveDestID can be 1, BOTH, ALL, NEIT etc.

This is commonly used by the PRESCfg module so that interpretTrac() can be called on the result and thus build up a map of track positions for all possible logical film outputs.

FILM Plotting Configuration from XML files

Creates FILM configurations from LgFormat XML files.

Created on Dec 14, 2011

exception TotalDepth.util.plot.FILMCfgXML.ExceptionFILMCfgXML

Specialisation of exception for FILMCfgXML module.

exception TotalDepth.util.plot.FILMCfgXML.ExceptionFILMCfgXMLRead

Specialisation of exception for FILMCfgXMLRead module.

exception TotalDepth.util.plot.FILMCfgXML.ExceptionFILMCfgXMLReadLookup

Specialisation of exception for FILMCfgXMLRead module when a lookup fails that would normally raise a KeyError.

class TotalDepth.util.plot.FILMCfgXML.PhysFilmCfgXMLRead(*root*)

Extracts FILM information from a single XML file root element.

TRAC_STANDARD_SPAN = 2

Default number of half-tracks to span

TRAC_UNIQUEID_TO_NON_STANDARD_SPAN = {'track12': 4, 'track23': 4, 'TrackFC1': 1, 'T

Map of track IDs to start track location in half-tracks

TRAC_UNIQUEID_TO_NON_STANDARD_START = {'track12': 2, 'track23': 4, 'TrackFC1': 4, 'T

Number of half-tracks of the start of the track, this is a fudge around deciding this from the order of the LgTrack elements

interpretTrac(*theTracStr*)

Turns TRAC information into left/right positions as Coord.Dim() objects and the number of half-tracks of the start and half-tracks covered. The later two values are used for stacking and packing the plot header and footer scales so that they take the minimum space. e.g. b'T23 ' returns: (the left position of T2, right

of T3, 4, 4). e.g. b'T2 ' returns: (the left position of T2, right of T2, 4, 2). Note: There is some fudging going on here

class TotalDepth.util.plot.FILMCfgXML.FilmCfgXMLRead(*directory=None*)

Contains the configuration equivalent to a complete FILM table from a set of XML files.

__init__(*directory=None*)

Constructor with a directory, all files in the directory (non-recursive) are read as LGFormat XML files. If dir is None then the “formats/” directory relative to this module is searched. If dir is an empty string then no search will be done - useful for testing with addXMLRoot(etree.fromstring(...)).

readDir(*d=None*)

Read a directory of XML files (not recursive).

addXMLRoot(*theRoot*)

Adds a parsed LgFormat XML document to the IR.

chOutpMnemInFilmId(*chOutp, filmID*)

Returns True if this curve appears in the film.

longStr(*verbose=1*)

Returns a long string of the XML UniqueIds and their description.

uniqueIds()

Returns the UniqueId values that I know about.

description(*theUID*)

Returns the XML description corresponding to the Unique ID or None if unknown.

rootNode(*theUID*)

Returns the XML root node corresponding to the Unique ID.

retAllFILMDests(*curveDestID*)

Returns an unordered list of FILM destinations for a curve destination. For example if curveDestID is b'BOTH' this might return [b'2 ', b'1 ']

retFILMDest(*filmDestID, curveDestID*)

Returns a PhysFilmCfgXMLRead object by matching curveDestID to the filmDestID. Returns None on failure. filmDestID and curveDestID are implementation specific e.g. for LIS the curveDestID can be 1, BOTH, ALL, NEIT etc. This is commonly used by the PRESCfg module so that interpretTrac() can be called on the result and thus build up a map of track positions for all possible logical film outputs.

PRES Plotting Configuration

Holds all the information to draw a curve on a plot.

TODO: Split this to:

- Generic: PRESCfg
- LIS specific: PRESCfgLIS
- XML specific: PRESCfgXML

Created on 20 Mar 2011

Examples of PRES records summaries:

| | | | | | | | | | |
|-----------------------------------|------|------|------|------|------|------|------|------|------|
| Table record (type 34) type: PRES | | | | | | | | | |
| MNEM | OUTP | STAT | TRAC | CODI | DEST | MODE | FILT | LEDG | REDG |
| ----- | | | | | | | | | |

| | | | | | | | | | |
|------|------|------|-----|------|------|------|----------|----------|---------|
| SP | SP | ALLO | T1 | LLIN | 1 | SHIF | 0.500000 | -80.0000 | 20.0000 |
| CALI | CALI | ALLO | T1 | LDAS | 1 | SHIF | 0.500000 | 5.00000 | 15.0000 |
| MINV | MINV | DISA | T1 | LLIN | 1 | SHIF | 0.500000 | 30.0000 | 0.00000 |
| MNOR | MNOR | DISA | T1 | LDAS | 1 | SHIF | 0.500000 | 30.0000 | 0.00000 |
| LLD | LLD | ALLO | T23 | LDAS | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| LLDB | LLD | ALLO | T2 | HDAS | 1 | GRAD | 0.500000 | 2000.00 | 200000. |
| LLG | LLG | DISA | T23 | LDAS | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| LLGB | LLG | DISA | T2 | HDAS | 1 | GRAD | 0.500000 | 2000.00 | 200000. |
| LLS | LLS | ALLO | T23 | LSPO | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| LLSB | LLS | ALLO | T2 | HSPO | 1 | GRAD | 0.500000 | 2000.00 | 200000. |
| MSFL | MSFL | ALLO | T23 | LLIN | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| 11 | DUMM | DISA | T1 | LLIN | NEIT | NB | 0.500000 | 0.00000 | 1.00000 |
| 12 | DUMM | DISA | T1 | LLIN | NEIT | NB | 0.500000 | 0.00000 | 1.00000 |
| 13 | DUMM | DISA | T1 | LLIN | NEIT | NB | 0.500000 | 0.00000 | 1.00000 |
| 14 | DUMM | DISA | T1 | LLIN | NEIT | NB | 0.500000 | 0.00000 | 1.00000 |
| 15 | DUMM | DISA | T1 | LLIN | NEIT | NB | 0.500000 | 0.00000 | 1.00000 |
| 16 | DUMM | DISA | T1 | LLIN | NEIT | NB | 0.500000 | 0.00000 | 1.00000 |
| 17 | DUMM | DISA | T1 | LLIN | NEIT | NB | 0.500000 | 0.00000 | 1.00000 |
| 18 | DUMM | DISA | T1 | LLIN | NEIT | NB | 0.500000 | 0.00000 | 1.00000 |
| 19 | DUMM | DISA | T1 | LLIN | NEIT | NB | 0.500000 | 0.00000 | 1.00000 |

Table record (type 34) type: PRES

| MNEM | OUTP | STAT | TRAC | CODI | DEST | MODE | FILT | LEDG | REDG |
|------|------|------|------|------|------|------|----------|-----------|-----------|
| NPHI | NPHI | ALLO | T23 | LDAS | 1 | SHIF | 0.500000 | 0.450000 | -0.150000 |
| DRHO | DRHO | ALLO | T3 | LSPO | 1 | NB | 0.500000 | -0.250000 | 0.250000 |
| PEF | PEF | ALLO | T23 | LGAP | 1 | SHIF | 0.500000 | 0.00000 | 10.0000 |
| SGR | | DISA | T1 | LLIN | 1 | SHIF | 0.500000 | 0.00000 | 300.000 |
| CGR | | DISA | T1 | LGAP | 1 | SHIF | 0.500000 | 0.00000 | 300.000 |
| TENS | TENS | DISA | T3 | LGAP | 1 | SHIF | 0.500000 | 14000.0 | 4000.00 |
| CAL | CALI | ALLO | T1 | LSPO | 1 | SHIF | 0.500000 | 5.00000 | 15.0000 |
| BS | BS | DISA | T1 | LGAP | 1 | SHIF | 0.500000 | 5.00000 | 15.0000 |
| FFLS | FFLS | DISA | T1 | LLIN | 2 | NB | 0.500000 | -0.150000 | 0.150000 |
| FFSS | FFSS | DISA | T1 | LDAS | 2 | NB | 0.500000 | -0.150000 | 0.150000 |
| LSHV | LSHV | DISA | T3 | LLIN | 2 | WRAP | 0.500000 | 2150.00 | 2250.00 |
| SSHV | SSHV | DISA | T3 | LDAS | 2 | WRAP | 0.500000 | 1950.00 | 2050.00 |
| FLS | FLS | DISA | T2 | LLIN | 2 | SHIF | 0.500000 | 0.00000 | 150.000 |
| FSS | FSS | DISA | T2 | LDAS | 2 | SHIF | 0.500000 | 0.00000 | 150.000 |
| RHOB | RHOB | ALLO | T23 | LLIN | 1 | SHIF | 0.500000 | 1.95000 | 2.95000 |
| PHIX | PHIX | ALLO | T1 | LLIN | 1 | NB | 0.500000 | 0.500000 | 0.00000 |

TRAC nomenclature:

<LH | RH> T n <m>

Or as a regex: `re.compile(r'^(LH|RH)*T(\d) (\d)*\s*$')`

But this is handled by FILMCfg.

Example:

```
$ python3 TableHistogram.py -k --name=PRES -l40 --col=TRAC ../../pLogicTestData/
↳ LIS/
Cmd: TableHistogram.py -k --name=PRES -l40 --col=TRAC ../../pLogicTestData/LIS/
2011-05-27 09:26:12,324 ERROR      Can not create Logical Record, error: can't convert
↳ negative value to unsigned int
2011-05-27 09:26:12,335 ERROR      Can not create Logical Record, error: can't convert
↳ negative value to unsigned int
```

```

2011-05-27 09:26:12,346 ERROR    Can not create Logical Record, error: can't convert
↳negative value to unsigned int
2011-05-27 09:26:13,086 ERROR    Can not read LIS file ../../pLogicTestData/LIS/
↳13576.S1 with error: Can not fit integer number of frames length 120 into LR length
↳824, modulo 104 [indirect size 0].
2011-05-27 09:26:13,907 ERROR    Can not read LIS file ../../pLogicTestData/LIS/
↳13610.S1 with error: Can not fit integer number of frames length 7176 into LR
↳length 13354, modulo 6178 [indirect size 0].
===== Count of all table entries =====
{"(34, b'PRES', b'TRAC', b'F1  ')": 4,
 "(34, b'PRES', b'TRAC', b'F2  ')": 4,
 "(34, b'PRES', b'TRAC', b'F3  ')": 4,
 "(34, b'PRES', b'TRAC', b'F4  ')": 3,
 "(34, b'PRES', b'TRAC', b'FD  ')": 4,
 "(34, b'PRES', b'TRAC', b'LHT1)": 4,
 "(34, b'PRES', b'TRAC', b'LHT2)": 8,
 "(34, b'PRES', b'TRAC', b'LHT3)": 59,
 "(34, b'PRES', b'TRAC', b'RHT1)": 4,
 "(34, b'PRES', b'TRAC', b'RHT2)": 22,
 "(34, b'PRES', b'TRAC', b'RHT3)": 63,
 "(34, b'PRES', b'TRAC', b'T1  ')": 2363,
 "(34, b'PRES', b'TRAC', b'T2  ')": 354,
 "(34, b'PRES', b'TRAC', b'T23 ')": 192,
 "(34, b'PRES', b'TRAC', b'T3  ')": 178,
 "(34, b'PRES', b'TRAC', b'TD  ')": 93,
 "(34, b'PRES', b'TRAC', b'XXX')": 18}
===== Count of all table entries END =====

```

DEST:

```

===== Count of all table entries =====
{"(34, b'PRES', b'DEST', b'1  ')": 457,
 "(34, b'PRES', b'DEST', b'123 ')": 2,
 "(34, b'PRES', b'DEST', b'134 ')": 20,
 "(34, b'PRES', b'DEST', b'2  ')": 139,
 "(34, b'PRES', b'DEST', b'5  ')": 26,
 "(34, b'PRES', b'DEST', b'6  ')": 122,
 "(34, b'PRES', b'DEST', b'8  ')": 16,
 "(34, b'PRES', b'DEST', b'A   ')": 19,
 "(34, b'PRES', b'DEST', b'ALL ')": 4,
 "(34, b'PRES', b'DEST', b'BOTH)": 774,
 "(34, b'PRES', b'DEST', b'D   ')": 63,
 "(34, b'PRES', b'DEST', b'E   ')": 60,
 "(34, b'PRES', b'DEST', b'J   ')": 52,
 "(34, b'PRES', b'DEST', b'K   ')": 13,
 "(34, b'PRES', b'DEST', b'NEIT)": 1610}
===== Count of all table entries END =====

```

MODE:

```

$ python3 TableHistogram.py -k --name=PRES -l40 --col=MODE ../../pLogicTestData/
↳LIS/
Cmd: TableHistogram.py -k --name=PRES -l40 --col=MODE ../../pLogicTestData/LIS/
2011-06-02 08:22:54,839 ERROR    Can not read LIS file ../../pLogicTestData/LIS/
↳13576.S1 with error: Can not fit integer number of frames length 120 into LR length
↳824, modulo 104 [indirect size 0].
2011-06-02 08:22:55,671 ERROR    Can not read LIS file ../../pLogicTestData/LIS/
↳13610.S1 with error: Can not fit integer number of frames length 7176 into LR
↳length 13354, modulo 6178 [indirect size 0].

```

```
===== Count of all table entries =====
{"(34, b'PRES', b'MODE', b'GRAD')": 245,
 "(34, b'PRES', b'MODE', b'NB  ')": 2329,
 "(34, b'PRES', b'MODE', b'SHIF')": 597,
 "(34, b'PRES', b'MODE', b'SWF  ')": 3,
 "(34, b'PRES', b'MODE', b'VDLN')": 3,
 "(34, b'PRES', b'MODE', b'WRAP')": 186,
 "(34, b'PRES', b'MODE', b'X10  ')": 10}
===== Count of all table entries END =====
```

COLO:

```
===== Count of all table entries =====
{"(34, b'PRES', b'COLO', b'000  ')": 173,
 "(34, b'PRES', b'COLO', b'002  ')": 3,
 "(34, b'PRES', b'COLO', b'003  ')": 6,
 "(34, b'PRES', b'COLO', b'004  ')": 33,
 "(34, b'PRES', b'COLO', b'014  ')": 6,
 "(34, b'PRES', b'COLO', b'020  ')": 9,
 "(34, b'PRES', b'COLO', b'021  ')": 8,
 "(34, b'PRES', b'COLO', b'030  ')": 34,
 "(34, b'PRES', b'COLO', b'034  ')": 2,
 "(34, b'PRES', b'COLO', b'044  ')": 6,
 "(34, b'PRES', b'COLO', b'104  ')": 3,
 "(34, b'PRES', b'COLO', b'134  ')": 14,
 "(34, b'PRES', b'COLO', b'203  ')": 3,
 "(34, b'PRES', b'COLO', b'221  ')": 3,
 "(34, b'PRES', b'COLO', b'312  ')": 10,
 "(34, b'PRES', b'COLO', b'400  ')": 44,
 "(34, b'PRES', b'COLO', b'404  ')": 6,
 "(34, b'PRES', b'COLO', b'420  ')": 9,
 "(34, b'PRES', b'COLO', b'430  ')": 17,
 "(34, b'PRES', b'COLO', b'AQUA')": 3,
 "(34, b'PRES', b'COLO', b'BLAC')": 1260,
 "(34, b'PRES', b'COLO', b'BLUE')": 8,
 "(34, b'PRES', b'COLO', b'GREE')": 37,
 "(34, b'PRES', b'COLO', b'RED  ')": 12}
===== Count of all table entries END =====
```

What are these numbers, RGB Base 5?

Track names F1 to F4 and FD.

This seems to be the nomenclature for four track plots. For example:

Table record (type 34) type: FILM

| MNEM | GCOD | GDEC | DEST | DSCA |
|-------|------|------|------|------|
| ----- | | | | |
| 8 | EB0 | --- | PF8 | D200 |
| A | LLLL | 1111 | PFA | DM |
| E | E4E | -4- | PFE | D200 |
| K | E4E | -4- | PFK | D500 |

Table record (type 34) type: PRES

| MNEM | OUTP | STAT | TRAC | CODI | DEST | MODE | FILT | LEDG | REDG |
|-------|------|------|------|------|------|------|------|------|------|
| ↪COLO | | | | | | | | | |

| | | | | | | | | | |
|-------|------|------|----|------|---|------|----------|-----------|------------|
| ----- | | | | | | | | | |
| ↪--- | | | | | | | | | |
| ... | | | | | | | | | |
| AX1A | AX | ALLO | F2 | LLIN | A | SHIF | 0.500000 | -9.00000 | 9.00000 ↪ |
| ↪400 | | | | | | | | | |
| AY1A | AY | ALLO | F2 | LSPO | A | SHIF | 0.500000 | -9.00000 | 9.00000 ↪ |
| ↪400 | | | | | | | | | |
| AZ1A | AZ | ALLO | F2 | LGAP | A | NB | 0.500000 | -9.00000 | 9.00000 ↪ |
| ↪400 | | | | | | | | | |
| AN1A | ANOR | ALLO | F4 | HDAS | A | NB | 0.500000 | 9.00000 | 11.0000 ↪ |
| ↪420 | | | | | | | | | |
| CS1A | CS | DISA | F1 | LDAS | A | NB | 0.500000 | 0.00000 | 150000. ↪ |
| ↪000 | | | | | | | | | |
| FX1A | FX | ALLO | F3 | LLIN | A | NB | 0.500000 | -0.700000 | 0.700000 ↪ |
| ↪003 | | | | | | | | | |
| FY1A | FY | ALLO | F3 | LGAP | A | NB | 0.500000 | -0.700000 | 0.700000 ↪ |
| ↪003 | | | | | | | | | |
| FZ1A | FZ | ALLO | F3 | LSPO | A | NB | 0.500000 | -0.700000 | 0.700000 ↪ |
| ↪003 | | | | | | | | | |
| FN1A | FNOR | ALLO | F4 | LLIN | A | NB | 0.500000 | 0.200000 | 0.700000 ↪ |
| ↪420 | | | | | | | | | |
| FI1A | FINC | ALLO | F4 | LGAP | A | NB | 1.00000 | 0.00000 | 90.0000 ↪ |
| ↪420 | | | | | | | | | |
| GA1A | GADZ | DISA | F1 | LLIN | A | NB | 1.00000 | -1.00000 | 1.00000 ↪ |
| ↪020 | | | | | | | | | |
| GP1A | GPV | DISA | F1 | LGAP | A | NB | 1.00000 | 14.0000 | 16.0000 ↪ |
| ↪020 | | | | | | | | | |
| GN1A | GNV | DISA | F1 | LDAS | A | NB | 1.00000 | -16.0000 | -14.0000 ↪ |
| ↪020 | | | | | | | | | |
| GM1A | GMT | DISA | F3 | HDAS | A | SHIF | 1.00000 | 80.0000 | 130.000 ↪ |
| ↪020 | | | | | | | | | |
| GA2A | GAT | DISA | F2 | HDAS | A | SHIF | 1.00000 | 80.0000 | 130.000 ↪ |
| ↪020 | | | | | | | | | |
| SI1A | SILO | DISA | FD | HLIN | A | NB | 1.00000 | 0.00000 | 20.0000 ↪ |
| ↪000 | | | | | | | | | |
| ST1A | STIT | DISA | FD | LLIN | A | NB | 1.00000 | 0.00000 | 20.0000 ↪ |
| ↪000 | | | | | | | | | |
| ST2A | STIA | ALLO | FD | LLIN | A | NB | 1.00000 | 0.00000 | 20.0000 ↪ |
| ↪000 | | | | | | | | | |
| TE1A | TENS | DISA | FD | LDAS | A | WRAP | 0.500000 | 2000.00 | 7000.00 ↪ |
| ↪000 | | | | | | | | | |
| ... | | | | | | | | | |

exception TotalDepth.util.plot.PRESCfg.**ExceptionPRESCfg**
Specialisation of exception for this module.

exception TotalDepth.util.plot.PRESCfg.**ExceptionLineTransBase**
Specialisation of exception for LineTransBase and descendants.

exception TotalDepth.util.plot.PRESCfg.**ExceptionLineTransBaseMath**
For LineTransBase and descendants where math errors occur.

exception TotalDepth.util.plot.PRESCfg.**ExceptionPRESCfgLISRead**
Specialisation of exception for this module.

exception TotalDepth.util.plot.PRESCfg.**ExceptionPresCfg**
Specialisation of exception for PresCfg.

exception TotalDepth.util.plot.PRESCfg.**ExceptionCurveCfg**

Specialisation of exception for CurveCfg.

exception TotalDepth.util.plot.PRESCfg.**ExceptionCurveCfgCtor**
Construction exception when making a CurveCfg object or descendant.

exception TotalDepth.util.plot.PRESCfg.**ExceptionCurveCfgLISRead**
Specialisation of exception for CurveCfgLISRead and its travails.

TotalDepth.util.plot.PRESCfg.**DEFAULT_LLINE_WIDTH_PX** = 0.5
Default light line width in pixels

TotalDepth.util.plot.PRESCfg.**DEFAULT_HLINE_WIDTH_PX** = 1.5
Default heavy line width in pixels

TotalDepth.util.plot.PRESCfg.**LIS_CODI_MAP** = {None: **Stroke**(width=0.5, colour='black', codi...
Maps LIS CODI mnemonics to a Stroke object: If either value is None an SVG attribute is not needed i.e. default SVG behaviour

TotalDepth.util.plot.PRESCfg.**LIS_COLO_MAP** = {Mnem(b'AQUA'): 'aqua', Mnem(b'BLAC'): 'black', ...
Maps LIS COLO mnemonics to CSS/SVG style colour specifications.

TotalDepth.util.plot.PRESCfg.**lisColo** (*theMnem*)
Returns a SVG colour as a string from a Mnem or None on failure.

TotalDepth.util.plot.PRESCfg.**coloStroke** (*theSt, theCm*)
Takes a Stroke object and returns a new stroke object with the colour replaced with the Color Mnem looked up, or determined from, the LIS_COLO_MAP.

TotalDepth.util.plot.PRESCfg.**BACKUP_NONE** = (1, -1)
No backup

TotalDepth.util.plot.PRESCfg.**BACKUP_ALL** = (0, 0)
Every backup i.e. 'wrap' Note: Plot.py has a way of limiting ludicrous backup lines to a sensible number; say 8

TotalDepth.util.plot.PRESCfg.**BACKUP_ONCE** = (-1, 1)
Single backup to left or right

TotalDepth.util.plot.PRESCfg.**BACKUP_TWICE** = (-2, 2)
Two backups to left or right

TotalDepth.util.plot.PRESCfg.**BACKUP_LEFT** = (0, -1)
Single backup to left only

TotalDepth.util.plot.PRESCfg.**BACKUP_RIGHT** = (1, 0)
Single backup to right only

TotalDepth.util.plot.PRESCfg.**BACKUP_FROM_MODE_MAP** = {None: (0, 0), b'SHIF': (-1, 1), b'GR...
Map of backup mode to internal representation

class TotalDepth.util.plot.PRESCfg.**LineTransBase** (*leftP, rightP, leftL, rightL, backup*)
Base class for line generators.

__init__ (*leftP, rightP, leftL, rightL, backup*)
 Ctor with values; leftP, rightP are physical positions as numbers. leftL, rightL are logical scales as numbers. backup is a pair (left, right). Will raise a ExceptionLineTransBase if leftP >= rightP.

leftL
 The left value of the curve scale as a number.

rightL
 The right value of the curve scale as a number.

L2P (*val*)
 Scale a given value to a dimension.

wrapPos (*val*)

For a given value returns a pair (wrap, pos). wrap is an integer number of times the curve is wrapped. pos is a float that is the physical plot position of the value. TODO: Benchmark this, it could be slow.

offScale (*w*)

Returns 0 if wrap integer is on scale depending on the backup setting. Returns -1 if off scale low, +1 if off scale high.

isOffScaleLeft (*w*)

True is wrap integer is off-scale low according to the backup setting.

isOffScaleRight (*w*)

True is wrap integer is off-scale high according to the backup setting.

__weakref__

list of weak references to the object (if defined)

class TotalDepth.util.plot.PRESCfg.**LineTransLin** (*leftP, rightP, leftL, rightL, backup=(0, 0)*)

Linear grid.

__init__ (*leftP, rightP, leftL, rightL, backup=(0, 0)*)

Ctor with values; leftP, rightP are physical positions as numbers. leftL, rightL are logical scales as numbers. backup is a pair (left, right).

L2P (*val*)

Scale a given value to a dimension.

wrapPos (*val*)

For a given value returns a pair (wrap, pos). wrap is an integer number of times the curve is wrapped. pos is a float that is the physical plot position of the value. TODO: Benchmark this, it could be slow.

class TotalDepth.util.plot.PRESCfg.**LineTransLog10** (*leftP, rightP, leftL, rightR, backup=(0, 0)*)

Logarithmic grid.

__init__ (*leftP, rightP, leftL, rightR, backup=(0, 0)*)

Ctor with values; leftP, rightP are physical positions as numbers. leftL, rightL are logical scales as numbers. backup is a pair (left, right).

L2P (*val*)

Scale a given value to a dimension.

wrapPos (*val*)

For a given value returns a pair (wrap, pos). wrap is an integer number of times the curve is wrapped. pos is a float that is the physical plot position of the value. TODO: Benchmark this, it could be slow.

class TotalDepth.util.plot.PRESCfg.**TrackWidthData** (*leftP, rightP, halfTrackStart, halfTracks*)

Used to record the physical width data of a track leftP, rightP are Coord.Dim objects. halfTrackStart, halfTracks are integers

__getnewargs__ ()

Return self as a plain tuple. Used by copy and pickle.

static **__new__** (*_cls, leftP, rightP, halfTrackStart, halfTracks*)

Create new instance of TrackWidthData(leftP, rightP, halfTrackStart, halfTracks)

__repr__ ()

Return a nicely formatted representation string

halfTrackStart

Alias for field number 2

halfTracks

Alias for field number 3

leftP

Alias for field number 0

rightP

Alias for field number 1

class TotalDepth.util.plot.PRESCfg.CurveCfg

Contains the configuration of a single curve.

__init__ ()

Populate attribute with reasonable default values. Second stage is to set: self.mnem, self.outp, self.trac, self.dest. Optionally other properties as well.

longStr ()

Returns a long descriptive string of the internal state.

tracWidthData (*theFilmID*)

Returns a TrackWidthData object for the film ID.

tracValueFunction (*theFilmID*)

Given a FILM ID (a Mnem() object) this returns a LineTransBase or derivation that describes how this curve is plotted on that film. In particular the return value will have a function wrapPos() for generating track positions from a value.

__weakref__

list of weak references to the object (if defined)

class TotalDepth.util.plot.PRESCfg.PresCfg

Contains the configuration equivalent to a complete PRES table.

add (*theCurveCfg*, *theFilmDestS*)

Adds to the IR. theCurveCfg is a CurveCfg object, theFilmDestS is a list of film destinations expanded from the FILM table e.g. if the destination is b'ALL' then all FILM destination mnemonics should be in the list.

keys ()

Returns the curve mnemonics.

__len__ ()

Number of curves in this table.

__getitem__ (*theCurvID*)

Returns the CurveCfg object corresponding to curve ID, a Mnem.Mnem object.

__contains__ (*theCurvID*)

Returns True if I have an entry for the curve ID, a Mnem.Mnem object.

__weakref__

list of weak references to the object (if defined)

hasCurvesForDest (*theDest*)

Returns True if there are curves that go to theDest i.e. FILM ID.

outpChIDs (*theDest*)

Returns a list of output channel IDs for a given film destination, a Mnem.Mnem object.

outpCurveIDs (*theDest*, *theOutp*)

Returns a list of channel IDs for a given film destination and output that feeds those curves. The curve data is accessible by __getitem__(). Arguments should be Mnem.Mnem objects

usesOutpChannel (*theDest, theOutp*)

Returns True if this PRES table + FILM destination uses theOutp ID. Arguments should be , a Mnem.Mnem objects.

class TotalDepth.util.plot.PRESCfg.PresCfgLISRead (*theLr, theFILMCfg*)

Information from a complete LIS PRES table.

__init__ (*theLr, theFILMCfg*)

Reads a LogiRec.Table object of type PRES and creates a CurveCfgLISRead for each row. theFILMCfg is expected to be a FILMCfgLISRead object.

Typical PRES table:

| MNEM | OUTP | STAT | TRAC | CODI | DEST | MODE | FILT | LEDG | REDG |
|---------|------|------|------|------|------|------|----------|-----------|------|
| ----- | | | | | | | | | |
| ↪----- | | | | | | | | | |
| NPHI | NPHI | ALLO | T23 | LDAS | 1 | SHIF | 0.500000 | 0.450000 | -0. |
| ↪150000 | | | | | | | | | |
| DRHO | DRHO | ALLO | T3 | LSPO | 1 | NB | 0.500000 | -0.250000 | 0. |
| ↪250000 | | | | | | | | | |
| PEF | PEF | ALLO | T23 | LGAP | 1 | SHIF | 0.500000 | 0.00000 | 10. |
| ↪0000 | | | | | | | | | |

PRES Plotting Configuration from XML files

Creates PRES configurations from LgFormat XML files.

Created on Dec 16, 2011

exception TotalDepth.util.plot.PRESCfgXML.ExceptionPRESCfgXML

Specialisation of exception for PRESCfgXML module.

exception TotalDepth.util.plot.PRESCfgXML.ExceptionCurveCfgXMLRead

Specialisation of exception for CurveCfgXMLRead module.

exception TotalDepth.util.plot.PRESCfgXML.ExceptionPresCfgXMLRead

Specialisation of exception for PresCfgXMLRead module.

TotalDepth.util.plot.PRESCfgXML.XML_CODI_MAP = {None: Stroke(width=0.5, colour='black', c
Maps LgFormat mnemonics to a Stroke object: If either value is None an SVG attribute is not needed i.e. default SVG behaviour

TotalDepth.util.plot.PRESCfgXML.BACKUP_FROM_MODE_MAP = {None: (0, 0), 'LG_LEFT_WRAPPED':
Maps LgFormat backup specifications to an internal representation Taken from the <WrapMode> element.

TotalDepth.util.plot.PRESCfgXML.BACKUP_FROM_COUNT_MAP = {None: (0, 0), '1': (-1, 1), '2':
Fallback mapping LgFormat backup specifications to an internal representation Taken from the <WrapCount> element.

class TotalDepth.util.plot.PRESCfgXML.CurveCfgXMLRead (*e, theTrac, theFILMCfg*)

Represents a single curve from an XML file specification

TRAC_XML_UNIQUEID_TO_PRES = {'depthTrack': b'TD ', 'DepthTrack': b'TD ', 'track1':
First column is observed tracks in the XML, note capitalisation inconsistencies. Second column is LIS DEST equivalent

__init__ (*e, theTrac, theFILMCfg*)

Creates a single CurveCfg object from an XML LgCurve element and populates a CurveCfg. e is the root LgCurve element. theTrac is the track name that this is being plotted on. theFILMCfg is expected to be a FilmCfgXMLRead object.

Example:

```
<LgCurve UniqueId="ROP5">
  <ChannelName>ROP5</ChannelName>
  <Color>0000FF</Color>
  <LeftLimit>500</LeftLimit>
  <RightLimit>0</RightLimit>
  <LineStyle>LG_DASH_LINE</LineStyle>
  <Thickness>1.75</Thickness>
  <WrapMode>LG_LEFT_WRAPPED</WrapMode>
</LgCurve>
Or:
<LgCurve UniqueId="PSR">
  <ChannelName>PSR</ChannelName>
  <Color>00C000</Color>
  <LeftLimit>0.2</LeftLimit>
  <RightLimit>2000</RightLimit>
  <Thickness>2</Thickness>
  <Transform>LG_LOGARITHMIC</Transform>
  <WrapCount>0</WrapCount>
</LgCurve>
```

class TotalDepth.util.plot.PRESCfgXML.PresCfgXMLRead(*theFILMCfg, theUniqueId*)
Extracts all curve presentation information from a single XML file.

__init__(*theFILMCfg, theUniqueId*)
Reads a XML and creates a CurveCfgXMLRead for each LgFormat/LgTrack/LgCurve element.
theFILMCfg is expected to be a FILMCfgXMLRead object.

Plotting Well Log API headers

Plots various headers as SVG. Of note is the API header

Created on Dec 30, 2011

exception TotalDepth.util.plot.LogHeader.ExceptionLogHeader
Exception for plotting Log Headers.

exception TotalDepth.util.plot.LogHeader.ExceptionLogHeaderLIS
Exception for plotting Log Headers from LIS data.

exception TotalDepth.util.plot.LogHeader.ExceptionLogHeaderLAS
Exception for plotting Log Headers from LAS data.

class TotalDepth.util.plot.LogHeader.Static(*x, y, w, d, text, font, size, tAttr, rAttr, mnem, xMnem*)

Tuple to describe static data locations If text is None then no text will be plotted If rAttr is None then no box will be plotted If mnem is non-None then a Mmem can be plotted at xMenm increment, a Coord.Dim()

d
Alias for field number 3

font
Alias for field number 5

mnem
Alias for field number 9

rAttr
Alias for field number 8

size
Alias for field number 6

tAttr
Alias for field number 7

text
Alias for field number 4

w
Alias for field number 2

x
Alias for field number 0

xMnem
Alias for field number 10

y
Alias for field number 1

TotalDepth.util.plot.LogHeader.**FONT_PROP** = 'Verdana'
Default font

TotalDepth.util.plot.LogHeader.**RECT_ATTRS_FINE** = {'fill': 'none', 'stroke': 'black', 'stroke-width': 1}
SVG attributes for a fine lined rectangle

TotalDepth.util.plot.LogHeader.**TEXT_ATTRS_FINE** = {'text-anchor': 'start'}
SVG attributes for a fine text

TotalDepth.util.plot.LogHeader.**TEXT_ATTRS_LARGE** = {'text-anchor': 'start', 'font-weight': 'bold'}
SVG attributes for a bold text

TotalDepth.util.plot.LogHeader.**TEXT_ATTRS_LARGE_WOB** = {'text-anchor': 'start', 'font-weight': 'bold', 'text-decoration': 'underline'}
SVG attributes for a large WOB text

TotalDepth.util.plot.LogHeader.**HEADER_PLOT_UNITS** = 'in'
Standard plot units used in the layout definition

class TotalDepth.util.plot.LogHeader.**APIHeaderBase** (*isTopOfLog=False*)
Base class to be used by APIHeaderLIS or APIHeaderLAS.

If isTopOfLog is True plot is rotated 90 deg as if to fit on top of a traditional log.

missingFields (*theWsd*)
Returns two sets: A set of mnemonics that could be plotted but are not in the Logical Record(s). A set of mnemonics that are in the Logical Record(s) but could not be plotted.

size ()
Returns a Coord.Box for my size, currently a single page on fan folded paper.

viewport (*theTl*)
The SVG viewport.

plot (*xS, theTl, theWsdS=None*)
Write the header to the SVG stream at position offset top left. theWsd is a list of records that contain well site data. Will raise ExceptionLogHeader is wrong type of Logical Record.

class TotalDepth.util.plot.LogHeader.**APIHeaderLIS** (*isTopOfLog=False*)
Can lay out an API header from LIS information, specifically a type 34 CONS record.

If isTopOfLog is True plot is rotated 90 deg as if to fit on top of a traditional log.

missingFields (*theWsd*)

Well site data (*theWsd*) in LIS is a list of CONS Logical Records.

Returns two sets:

A set of mnemonics that could be plotted but are not in the Logical Record(s).

A set of mnemonics that are in the Logical Record(s) but could not be plotted.

lrDataCount (*theLrS*)

Returns the number of Mnem's in MNEM_SET that could be plotted in a header that are found in all the Logical Records.

class TotalDepth.util.plot.LogHeader.**APIHeaderLAS** (*isTopOfLog=False*)

Can lay out an API header from a representation of a LAS file.

LIS_MNEM_TO_LAS_MNEM = {'BLI': 'STRT', 'TLI': 'STOP', 'CN': 'COMP', 'WN': 'WELL', 'FN'

Some conversions from LIS standard to LAS standard All as truncated ascii strings i.e. using pStr(strip=True)

missingFields (*theLasFile*)

Returns two sets:

A set of mnemonics that could be plotted but are not in the Logical Record(s).

A set of mnemonics that are in the Logical Record(s) but could not be plotted.

Plotting Well Logs

Created on 28 Feb 2011

Plotting LIS data requires these components:

- A PlotConfig object
- A data set (e.g. a LogPass with a FrameSet).
- An output driver (e.g. screen, print PDF, web SVG).

User creates a PlotConfig (this reflects a PRES table). This is reusable.

User specifies a data set (from, to, channels etc.). e.g. Invoke LogPass.setFrameSet(File, theFrameSlice=theFrameSlice, theChList=theChList)

User says 'plot this data set with this configuration to this output device'. e.g. Plot(PlotConfig, LogPass, PlotDevice) Plot uses LogPass.genChScValues(ch, sc) to plot individual curves.

Lacunae

Area plotting. Caching (e.g. SVG fragments - is this worth it?)

PlotConfig

PlotTracks

Typically a three track (+depth) have these dimensions in inches:

| Track | Left | Right | Width |
|-------|------|-------|-------|
| 1 | 0 | 2.4 | 2.4 |
| Depth | 2.4 | 3.2 | 0.8 |
| 2 | 3.2 | 5.6 | 2.4 |
| 3 | 5.6 | 8.0 | 2.4 |

Track names can be split (e.g. LHT1 is left hand track 1) or merged (T23 is spread across tracks two and three).

Examples of PRES and FILM records:

| Table record (type 34) type: PRES | | | | | | | | | |
|-----------------------------------|------|------|------|------|------|------|----------|-----------|-----------|
| MNEM | OUTP | STAT | TRAC | CODI | DEST | MODE | FILT | LEDG | REDG |
| ----- | | | | | | | | | |
| SP | SP | ALLO | T1 | LLIN | 1 | SHIF | 0.500000 | -80.0000 | 20.0000 |
| CALI | CALI | ALLO | T1 | LDAS | 1 | SHIF | 0.500000 | 5.00000 | 15.0000 |
| MINV | MINV | DISA | T1 | LLIN | 1 | SHIF | 0.500000 | 30.0000 | 0.00000 |
| MNOR | MNOR | DISA | T1 | LDAS | 1 | SHIF | 0.500000 | 30.0000 | 0.00000 |
| LLD | LLD | ALLO | T23 | LDAS | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| LLDB | LLD | ALLO | T2 | HDAS | 1 | GRAD | 0.500000 | 2000.00 | 200000. |
| LLG | LLG | DISA | T23 | LDAS | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| LLGB | LLG | DISA | T2 | HDAS | 1 | GRAD | 0.500000 | 2000.00 | 200000. |
| LLS | LLS | ALLO | T23 | LSPO | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| LLSB | LLS | ALLO | T2 | HSPO | 1 | GRAD | 0.500000 | 2000.00 | 200000. |
| MSFL | MSFL | ALLO | T23 | LLIN | 1 | GRAD | 0.500000 | 0.200000 | 2000.00 |
| Table record (type 34) type: FILM | | | | | | | | | |
| MNEM | GCOD | GDEC | DEST | DSCA | | | | | |
| ----- | | | | | | | | | |
| 1 | E20 | -4-- | PF1 | D200 | | | | | |
| 2 | EEE | ---- | PF2 | D200 | | | | | |
| Table record (type 34) type: PRES | | | | | | | | | |
| MNEM | OUTP | STAT | TRAC | CODI | DEST | MODE | FILT | LEDG | REDG |
| ----- | | | | | | | | | |
| NPHI | NPHI | ALLO | T23 | LDAS | 1 | SHIF | 0.500000 | 0.450000 | -0.150000 |
| DRHO | DRHO | ALLO | T3 | LSPO | 1 | NB | 0.500000 | -0.250000 | 0.250000 |
| PEF | PEF | ALLO | T23 | LGAP | 1 | SHIF | 0.500000 | 0.00000 | 10.0000 |
| SGR | | DISA | T1 | LLIN | 1 | SHIF | 0.500000 | 0.00000 | 300.000 |
| CGR | | DISA | T1 | LGAP | 1 | SHIF | 0.500000 | 0.00000 | 300.000 |
| TENS | TENS | DISA | T3 | LGAP | 1 | SHIF | 0.500000 | 14000.0 | 4000.00 |
| CAL | CALI | ALLO | T1 | LSPO | 1 | SHIF | 0.500000 | 5.00000 | 15.0000 |
| BS | BS | DISA | T1 | LGAP | 1 | SHIF | 0.500000 | 5.00000 | 15.0000 |
| FFLS | FFLS | DISA | T1 | LLIN | 2 | NB | 0.500000 | -0.150000 | 0.150000 |
| FFSS | FFSS | DISA | T1 | LDAS | 2 | NB | 0.500000 | -0.150000 | 0.150000 |
| LSHV | LSHV | DISA | T3 | LLIN | 2 | WRAP | 0.500000 | 2150.00 | 2250.00 |
| SSHV | SSHV | DISA | T3 | LDAS | 2 | WRAP | 0.500000 | 1950.00 | 2050.00 |
| FLS | FLS | DISA | T2 | LLIN | 2 | SHIF | 0.500000 | 0.00000 | 150.000 |
| FSS | FSS | DISA | T2 | LDAS | 2 | SHIF | 0.500000 | 0.00000 | 150.000 |
| RHOB | RHOB | ALLO | T23 | LLIN | 1 | SHIF | 0.500000 | 1.95000 | 2.95000 |
| PHIX | PHIX | ALLO | T1 | LLIN | 1 | NB | 0.500000 | 0.500000 | 0.00000 |

`TotalDepth.util.plot.Plot.COMMENTS_IN_SVG_TRACE = False`

Allows detailed trace comments to appear in the SVG

`TotalDepth.util.plot.Plot.COMMENTS_IN_SVG_SECTION = True`

A few comments in SVG to delinialte header, Grid, Xaxis, curves etc

`TotalDepth.util.plot.Plot.COMMENTS_IN_SVG_SECTION_WIDTH = 40`

Width of comment for sections

`TotalDepth.util.plot.Plot.COMMENTS_IN_SVG_SECTION_LEVEL_TUPLE = ('=', '.', '^')`

Map of section level to comment padding character

exception `TotalDepth.util.plot.Plot.ExceptionTotalDepthLISPlot`

Exception for plotting.

exception `TotalDepth.util.plot.Plot.ExceptionTotalDepthPlotRoll`

Exception for plotting.

class `TotalDepth.util.plot.Plot.CurvePlotScale`

Holds a minimal amount of curve plot scale and so on for the layout of the scale pane at each end of the log.

halfTrackStart is the start of the curve for a standard three track log T1=0, TD=2, T2=4, T3=6

halfTracks is the curve span as an integer so T23=4 LHT1=1 and so on.

`__lt__` (*other*)

Slightly weird sort order, larger halfTracks come first then names.

class `TotalDepth.util.plot.Plot.ScaleSliceCurve` (*slice, curveName, start, span*)

`__getnewargs__` ()

Return self as a plain tuple. Used by copy and pickle.

static `__new__` (*_cls, slice, curveName, start, span*)

Create new instance of ScaleSliceCurve(slice, curveName, start, span)

`__repr__` ()

Return a nicely formatted representation string

curveName

Alias for field number 1

slice

Alias for field number 0

span

Alias for field number 3

start

Alias for field number 2

class `TotalDepth.util.plot.Plot.CurvePlotScaleSlotMap` (*theCpsS*)

Keeps track of which slots are available for putting the curve scales in at the top and bottom of the log. This scale are is divided into slices that span the plot from left to right. These slices are subdivided into slots that correspond to a half-track in that slice.

`__init__` (*theCpsS*)

Ctor with a list of CurvePlotScale objects (can be unsorted).

reset ()

Clears the slot map for the current slice.

```

|-----|
|               Plot margin               |
| .....|
| *****|
| .*                                           .*|
| .*           Optional header e.g. API header           .*|
| .*                                           .*|
| *****|
| ++++++|
| .+                                           +.|
| .+           Scales (legends) at the top of the plot.           +.|
| .+                                           +.|
| ++++++|
| .^..... -- X Stop (if up log) -- ^.....|
| .^                                           ^.|
| .^                                           ^.|
| .^                                           ^.|
| .^           Main log plotted here           ^.|
| .^                                           ^.|
| .^                                           ^.|
| .^                                           ^.|
| .^..... -- X Start (if up log) -- ^.....|
| ++++++|
| .+                                           +.|
| .+           Scales (legends) at the bottom of the plot.           +.|
|-----|

```

```

| .+ |
| .+++++ |
| .***** |
| . * |
| . * Optional trailer e.g. calibration record * |
| . * * |
| .***** |
| ..... |
| Plot margin |
| ----- |

```

__init__ (*theXStart*, *theXStop*, *theScale*, *theLegendDepth*, *theHeadDepth*=Dim(value=0, units='in'), *theTailDepth*=Dim(value=0, units='in'), *plotUp*=True, *theWidth*=Dim(value=8.5, units='in'), *theMargin*=Margin(left=Dim(value=0.25, units='in'), right=Dim(value=0.25, units='in'), top=Dim(value=0.25, units='in'), bottom=Dim(value=0.25, units='in'))

Initialise with:

theXStart The X start position as an EngVal.

theXStop The X stop position as an EngVal.

theScale The plot scale as a number.

theLegendDepth A Coord.Dim() that is the depth of the scales used in the header and footer.

theHeadDepth A Coord.Dim() that is the depth of any log header.

theTailDepth A Coord.Dim() that is the depth of any log trailer.

plotUp, bool True if X start is at the bottom of the main pane.

theWidth The absolute width of the plot as a Coord.Dim().

theMargin A Coord.Margin() that describes the untouchable edges of the plot.

viewBox

The overall size of the plot.

width

The overall width as a number in PlotConstants.DEFAULT_PLOT_UNITS.

depth

The overall width as a number in PlotConstants.DEFAULT_PLOT_UNITS.

widthDim

The overall width as a Coord.Dim().

depthDim

The overall width as a Coord.Dim().

trackTopLeft

“A Coord.Pt() that is the top left of the pane that tracks are plotted within.

mainPanePlotDepth

The depth of the plot of the main pane as a Coord.Dim().

availableWidth

The available width inside the margins.

retHeadPane()

Returns a pair of top-left Coord.Pt(), Coord.Box() for the top header where the header goes.

retLegendPane(isTop)

Returns a pair of top-left Coord.Pt(), Coord.Box() for the top or bottom legend pane where the scales go.

retMainPane()

Returns a pair of top-left Coord.Pt(), Coord.Box() for the pane where the main log goes.

retTailPane()

Returns a pair of top-left Coord.Pt(), Coord.Box() for the pane where the trailer goes.

xDepth(*theX*)

Returns a Coord.Dim() on the main pane that corresponds to theX as a number or an EngVal. If this is a number it is expected to be in the units of the xStart/xStop in the constructor.

polyLinePt(*theX*, *theTracPos*)

Returns a Coord.Pt from theX axis value (or EngVal) and theTracPos that is a value in DEFAULT_PLOT_UNITS, for example given by a tracValueFunction. The Coord.Pt() will be scaled by VIEW_BOX_UNITS_PER_PLOT_UNITS.

retMainPaneStart()

Returns the start Coord.Pt() for the pane where the main log goes. For and upPlot this will be pane-bottom-left, for a downPlot this will be pane-top-left.

__weakref__

list of weak references to the object (if defined)

class TotalDepth.util.plot.Plot.**Plot**(*theFilmCfg*, *thePresCfg*, *theScale=0*)

Defines a plot configuration. The basic architecture follows the data. The constructor takes all the static data, typically this can be obtained from the PRES and FILE tables. The dynamic (or user selected data) is passed in to plotLogPassLIS(). This is intended as a single Plot object might be used multiple times (e.g. on 'scroll up').

TITLE_FONT_FAMILY = 'Verdana'

Title font

TITLE_FONT_SIZE = 10

Title font size

LEGEND_DEPTH_PER_CURVE = Dim(value=0.5, units='in')

How much depth to give each legend (curve scale) at the top and bottom of the log

LEGEND_DEPTH_SPARE = Dim(value=0.5, units='in')

How much spare depth to give over the legend (curve scale) sections at the top and bottom of the log

LEGEND_HORIZONTAL_LINE_DEPTH_PROPORTION = 0.625

Where the curve line in the legend section appears as a proportion of LEGEND_DEPTH_PER_CURVE

LEGEND_ARROW_DISPLAY = True

Arrow heads on legend scales

LEGEND_ARROW_WIDTH = Dim(value=0.08, units='in')

Arrow head width on legend scales

LEGEND_ARROW_DEPTH = Dim(value=0.04, units='in')

Arrow head depth on legend scales

LEGEND_ARROW_WIDTH_PX = 0.75

Arrow head line width on legend scales

CURVE_LEGEND_FONT_FAMILY = 'Courier'

Legend font.

CURVE_LEGEND_FONT_SIZE = 9

Legend font family.

MICRO_MARGIN = Dim(value=0.04, units='in')

This is just a very small margin to provide a tiny bit of whitespace between elements in certain places

MAX_BACKUP_TRACK_CROSSING_LINES = 4

Maximum number of backup lines that can cross a single track in a single X step See the source of `_filterCrossLineList()` for an explanation.

xScale (*theFilmID*)

Returns the X axis scale as a number given the FILM ID.

filmIds ()

Returns an unordered list of FILM IDs.

hasDataToPlotLIS (*theLogPass, theFilmId*)

Returns True if a call to `plotLogPassLIS()` is likely to lead to some plot data being produced.

plotLogPassLIS (*theLisFile, theLogPass, theXStart, theXStop, theFilmId, theFpOut, frameStep=1, title="", lrCONS=None, timerS=None*)

Plot a part of a LogPass and returns a list of Channel IDs plotted.

theLisFile The LIS File object.

theLogPass A LogPass object, the FrameSet will be populated here.

theXStart The start X axis position as an EngVal.

theXStop The stop X axis position as an EngVal.

theFilmId The ID of the output device from the film table

theFpOut A file path for the output SVG.

frameStep Integer number of frame steps, 1 is all frames.

title A string for the title that will appear in `LEGEND_DEPTH_SPARE`

lrCONS A CONS Logical Record that will be used to plot an API header in SVG.

timerS Optional `ExecTimer.ExecTimerList` for performance measurement.

TODO: If title is empty do not use the space `self.LEGEND_DEPTH_SPARE`

hasDataToPlotLAS (*theLasFile, theFilmId*)

Returns True if a call to `plotLogPassLIS()` is likely to lead to some plot data being produced.

plotLogPassLAS (*theLasFile, theXStart, theXStop, theFilmId, theFpOut, frameStep=1, title="", plot-Header=False, timerS=None*)

Plot a part of a LogPass and returns a list of Channel IDs plotted.

theLisFile - The LIS File object.

theLogPass - A LogPass object, the FrameSet will be populated here.

theXStart - The start X axis position as an EngVal.

theXStop - The stop X axis position as an EngVal.

theFilmId - The ID of the output device from the film table

theFpOut - A file path for the output SVG.

frameStep - Integer number of frame steps, 1 is all frames.

title - A string for the title that will appear in `LEGEND_DEPTH_SPARE`

lrCONS - A CONS Logical Record that will be used to plot an API header in SVG.

timerS - Optional `ExecTimer.ExecTimerList` for performance measurement.

TODO: If title is empty do not use the space `self.LEGEND_DEPTH_SPARE`

`__weakref__`

list of weak references to the object (if defined)

class `TotalDepth.util.plot.Plot.PlotReadLIS` (*lrFILM*, *lrPRES*, *lrAREA=None*, *lr-PIP=None*, *theScale=0*)
A subclass of `Plot` that is configured from `FILM`, `PRES` and (optionally) `AREA`, `PIP` Logical Records.

class `TotalDepth.util.plot.Plot.PlotReadXML` (*uniqueId*, *theScale=0*)
A subclass of `Plot` that is configured from XML file(s) using `LgFormat`.

1.12 A Bag Full of TODO's

This is just a gathering area for work items that should be done at some point.

TotalDepth is currently at **Alpha**, release version 0.2.0.

1.12.1 Current Release

This lists known work (and area) that are known lacuna in the Alpha release.

LIS Format Support

General

- XNAM direct support for LIS-A

LIS Index

- Various forms of persistence: XML, Pickle, JSON (no).
- Insert or append binary representation of the index to the LIS file.

LIS FrameSet/LogPass

- Provide a numpy view on each sub-channel.
- X Axis quality i.e. duplicate, missing frames.
- Change up log to down log (needs to rearrange multi-sampled channels).
- Clearer view on what 'frame spacing' actually is.

Representation Codes

- Check overflow/underflow on write.

LAS Format Support

- Read directly from .zip files.
- Version 3.0 support.
- Merge ~O section into ~P if correct format.
- Consistency checking of mutual data such as STRT/STOP/STEP

Plotting

- There is quite a lot of technical debt built up since we added LgFormat support, this area needs a review.
- Header: Some mud parameters being dropped.
- Benchmarks to characterise execution time and profiling.

1.12.2 Future Releases

This lists known work (and area) that are would be nice to have in future releases.

Format Support

Wireline Formats

- RP66v1
- RP66v2
- WellLogML?
- ATLAS BIT?

Seismic Formats

- SEG-Y
- SEG-D?
- Other SEG formats

Miscellaneous Formats

- Position

1.13 Glossary

Backup Mode A means of specifying what happens to plotted lines when they go off scale. Typical examples are None (all intermediate data is lost) and ‘wrap’ (all data is plotted with lines at modulo scale).

Data Format Specification Record [*LIS*] An EFLR that describes type 0 or type 1 binary IFLRs containing log data. A DFSR consists of a set of Entry Blocks followed by a list of Datum Specification Blocks.

NOTE: The LIS specification associates a particular DFSR type 0 | 1 with binary IFLRs of type 0 | 1. These collections will be independent of each other and thus permits the simultaneous recording of entirely different data sets. In practice however this rarely happens and it is debatable whether any or all LIS processing implementations support this.

Datum Specification Block [*LIS*] A fixed format data block that defines the characteristics of a single, independent, data channel in a DFSR.

DFSR See *Data Format Specification Record*

DLIS This adds schema specific semantics to *RP66*.

DSB See *Datum Specification Block*.

EFLR See *Explicitly Formatted Logical Record*.

Engineering Value A numeric value together with its units of measure.

Entry Block [*LIS*] A variable length block of data that describes a static value in DFSR. This value is local to a Log Pass. For example an Entry Block might describe the NULL or absent value for any channel in a Log Pass.

Explicitly Formatted Logical Record This is an internally complete, self-describing record.

Frame An array of values for each channel at a particular depth (or time).

Frame Set A set of frames representing multi-channel data that is typically depth or time series based.

IFLR See *Indirectly Formatted Logical Record*.

Indirectly Formatted Logical Record This is a Logical Record whose format is only completely described by another EFLR. The EFLR that describes an IFLR might be identified formally; for example by a specific reference to an EFLR (as in *RP66*) or informally; by some heuristic (as in *LIS*) such as “the immediately prior Logical Record that is type 64”.

LIS

LIS-79 Log Information Standard. The original file format used by Schlumberger from 1979 onwards. It is a *proprietary, de-facto* standard.

LIS-A Enhanced Log Information Standard. This adds somewhat to the [*LIS-79*] standard.

Log Pass A TotalDepth term that describes a continuous body of logging data such as “Repeat Section” or “Main Log”. In the *LIS* format this is defined by a single Logical Record, the *DFSR*, plus multiple type 0 or type 1 Logical Records that the DFSR describes.

Logical Record [*LIS*] A formal record from a LIS file. Logical Records consist of a header and optional payload. The Logical Records *type* is identified in the header. The interpretation of the payload of (some) Logical Records types is defined in the LIS standard. Logical Records consist of the payloads of one or more Physical Records. Logical Records are either EFLR or IFLR records.

LRH

Logical Record header The bytes that describe the type and attributes of a Logical Record.

Mnem See *Mnemonic*.

Mnemonic [*LIS*] A four byte identifier that is human readable e.g. RHOB for Bulk Density.

Physical Record [*LIS*] A formal record in a LIS file. Physical Records consist of a header, optional payload and optional trailer. Logical Records consist of the payloads of one or more Physical Records.

RepCode See *Representation Code*.

Representation Code A code, usually an integer, that describes how a particular run of bytes should be interpreted as a value (number, string etc.). For example in the LIS standard representation code 68 describes a 32 bit floating point format.

RP66 *Recommended Practice 66* is an API standard that describes a more advanced file format for, among other things, wireline logs. Comes in two flavours version 1 and version 2. Often (and incorrectly) referred to as *DLIS*.

UOM *Unit of Measure* for engineering values. In *LIS* these are a set of fixed terms organised into several categories, such as *Linear Length*. Values can only be converted between units of in the same category. In *RP66* these are composed by a BNF parseable string.

Xaxis

X Axis The index channel in an array, for example an array of frames. Typically depth or time.

1.14 TotalDepth Licence

1.14.1 OpenSource Licence

TotalDepth is released under GPL 2.:

```
GNU GENERAL PUBLIC LICENSE
Version 2, June 1991

Copyright (C) 1989, 1991 Free Software Foundation, Inc.,
51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA
Everyone is permitted to copy and distribute verbatim copies
of this license document, but changing it is not allowed.

Preamble

The licenses for most software are designed to take away your
freedom to share and change it. By contrast, the GNU General Public
License is intended to guarantee your freedom to share and change free
software--to make sure the software is free for all its users. This
General Public License applies to most of the Free Software
Foundation's software and to any other program whose authors commit to
using it. (Some other Free Software Foundation software is covered by
the GNU Lesser General Public License instead.) You can apply it to
your programs, too.

When we speak of free software, we are referring to freedom, not
price. Our General Public Licenses are designed to make sure that you
have the freedom to distribute copies of free software (and charge for
this service if you wish), that you receive source code or can get it
if you want it, that you can change the software or use pieces of it
in new free programs; and that you know you can do these things.

To protect your rights, we need to make restrictions that forbid
anyone to deny you these rights or to ask you to surrender the rights.
These restrictions translate to certain responsibilities for you if you
distribute copies of the software, or if you modify it.

For example, if you distribute copies of such a program, whether
gratis or for a fee, you must give the recipients all the rights that
you have. You must make sure that they, too, receive or can get the
```

source code. And you must show them these terms so they know their rights.

We protect your rights with two steps: (1) copyright the software, and (2) offer you this license which gives you legal permission to copy, distribute and/or modify the software.

Also, for each author's protection and ours, we want to make certain that everyone understands that there is no warranty for this free software. If the software is modified by someone else and passed on, we want its recipients to know that what they have is not the original, so that any problems introduced by others will not reflect on the original authors' reputations.

Finally, any free program is threatened constantly by software patents. We wish to avoid the danger that redistributors of a free program will individually obtain patent licenses, in effect making the program proprietary. To prevent this, we have made it clear that any patent must be licensed for everyone's free use or not licensed at all.

The precise terms and conditions for copying, distribution and modification follow.

GNU GENERAL PUBLIC LICENSE TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

0. This License applies to any program or other work which contains a notice placed by the copyright holder saying it may be distributed under the terms of this General Public License. The "Program", below, refers to any such program or work, and a "work based on the Program" means either the Program or any derivative work under copyright law: that is to say, a work containing the Program or a portion of it, either verbatim or with modifications and/or translated into another language. (Hereinafter, translation is included without limitation in the term "modification".) Each licensee is addressed as "you".

Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running the Program is not restricted, and the output from the Program is covered only if its contents constitute a work based on the Program (independent of having been made by running the Program). Whether that is true depends on what the Program does.

1. You may copy and distribute verbatim copies of the Program's source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and give any other recipients of the Program a copy of this License along with the Program.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.

2. You may modify your copy or copies of the Program or any portion of it, thus forming a work based on the Program, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:

- a) You must cause the modified files to carry prominent notices stating that you changed the files and the date of any change.
- b) You must cause any work that you distribute or publish, that in whole or in part contains or is derived from the Program or any part thereof, to be licensed as a whole at no charge to all third parties under the terms of this License.
- c) If the modified program normally reads commands interactively when run, you must cause it, when started running for such interactive use in the most ordinary way, to print or display an announcement including an appropriate copyright notice and a notice that there is no warranty (or else, saying that you provide a warranty) and that users may redistribute the program under these conditions, and telling the user how to view a copy of this License. (Exception: if the Program itself is interactive but does not normally print such an announcement, your work based on the Program is not required to print an announcement.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Program, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Program, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Program.

In addition, mere aggregation of another work not based on the Program with the Program (or with a work based on the Program) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

3. You may copy and distribute the Program (or a work based on it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you also do one of the following:

- a) Accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,
- b) Accompany it with a written offer, valid for at least three years, to give any third party, for a charge no more than your cost of physically performing source distribution, a complete machine-readable copy of the corresponding source code, to be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,
- c) Accompany it with the information you received as to the offer to distribute corresponding source code. (This alternative is allowed only for noncommercial distribution and only if you

received the program in object code or executable form with such an offer, in accord with Subsection b above.)

The source code for a work means the preferred form of the work for making modifications to it. For an executable work, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the executable. However, as a special exception, the source code distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

If distribution of executable or object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place counts as distribution of the source code, even though third parties are not compelled to copy the source along with the object code.

4. You may not copy, modify, sublicense, or distribute the Program except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense or distribute the Program is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

5. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Program or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Program (or any work based on the Program), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Program or works based on it.

6. Each time you redistribute the Program (or any work based on the Program), the recipient automatically receives a license from the original licensor to copy, distribute or modify the Program subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties to this License.

7. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Program at all. For example, if a patent license would not permit royalty-free redistribution of the Program by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Program.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system, which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

8. If the distribution and/or use of the Program is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Program under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.

9. The Free Software Foundation may publish revised and/or new versions of the General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Program specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Program does not specify a version number of this License, you may choose any version ever published by the Free Software Foundation.

10. If you wish to incorporate parts of the Program into other free programs whose distribution conditions are different, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

NO WARRANTY

11. BECAUSE THE PROGRAM IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE PROGRAM, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE PROGRAM "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING,

REPAIR OR CORRECTION.

12. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE PROGRAM AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PROGRAM (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE PROGRAM TO OPERATE WITH ANY OTHER PROGRAMS), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

END OF TERMS AND CONDITIONS

How to Apply These Terms to Your New Programs

If you develop a new program, and you want it to be of the greatest possible use to the public, the best way to achieve this is to make it free software which everyone can redistribute and change under these terms.

To do so, attach the following notices to the program. It is safest to attach them to the start of each source file to most effectively convey the exclusion of warranty; and each file should have at least the "copyright" line and a pointer to where the full notice is found.

```
<one line to give the program's name and a brief idea of what it does.>
Copyright (C) <year> <name of author>
```

```
This program is free software; you can redistribute it and/or modify
it under the terms of the GNU General Public License as published by
the Free Software Foundation; either version 2 of the License, or
(at your option) any later version.
```

```
This program is distributed in the hope that it will be useful,
but WITHOUT ANY WARRANTY; without even the implied warranty of
MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
GNU General Public License for more details.
```

```
You should have received a copy of the GNU General Public License along
with this program; if not, write to the Free Software Foundation, Inc.,
51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA.
```

Also add information on how to contact you by electronic and paper mail.

If the program is interactive, make it output a short notice like this when it starts in an interactive mode:

```
Gnomovision version 69, Copyright (C) year name of author
Gnomovision comes with ABSOLUTELY NO WARRANTY; for details type `show w'.
This is free software, and you are welcome to redistribute it
under certain conditions; type `show c' for details.
```

The hypothetical commands `show w' and `show c' should show the appropriate parts of the General Public License. Of course, the commands you use may be called something other than `show w' and `show c'; they could even be mouse-clicks or menu items--whatever suits your program.

You should also get your employer (if you work as a programmer) or your

```
school, if any, to sign a "copyright disclaimer" for the program, if
necessary. Here is a sample; alter the names:
```

```
Yoyodyne, Inc., hereby disclaims all copyright interest in the program
`Gnomovision' (which makes passes at compilers) written by James Hacker.
```

```
<signature of Ty Coon>, 1 April 1989
Ty Coon, President of Vice
```

```
This General Public License does not permit incorporating your program into
proprietary programs. If your program is a subroutine library, you may
consider it more useful to permit linking proprietary applications with the
library. If this is what you want to do, use the GNU Lesser General
Public License instead of this License.
```

1.14.2 Other Licences

For other licences contact: apaulross@gmail.com

1.15 Credits

1.15.1 Development Lead

- Paul Ross <apaulross@gmail.com>

1.15.2 Contributors

None yet. Why not be the first?

1.16 Contributing

Contributions are welcome, and they are greatly appreciated! Every little bit helps, and credit will always be given.

You can contribute in many ways:

1.16.1 Types of Contributions

Report Bugs

Report bugs at <https://github.com/paulross/TotalDepth/issues>.

If you are reporting a bug, please include:

- Your operating system name and version.
- Any details about your local setup that might be helpful in troubleshooting.
- Detailed steps to reproduce the bug.

Fix Bugs

Look through the GitHub issues for bugs. Anything tagged with “bug” and “help wanted” is open to whoever wants to implement it.

Implement Features

Look through the GitHub issues for features. Anything tagged with “enhancement” and “help wanted” is open to whoever wants to implement it.

Write Documentation

TotalDepth could always use more documentation, whether as part of the official TotalDepth docs, in docstrings, or even on the web in blog posts, articles, and such.

Submit Feedback

The best way to send feedback is to file an issue at <https://github.com/paulross/TotalDepth/issues>.

If you are proposing a feature:

- Explain in detail how it would work.
- Keep the scope as narrow as possible, to make it easier to implement.
- Remember that this is a volunteer-driven project, and that contributions are welcome :)

1.16.2 Get Started!

Ready to contribute? Here’s how to set up *TotalDepth* for local development.

1. Fork the *TotalDepth* repo on GitHub.
2. Clone your fork locally:

```
$ git clone git@github.com:paulross/TotalDepth.git
```

3. Install your local copy into a virtualenv. Assuming you have virtualenvwrapper installed, this is how you set up your fork for local development:

```
$ mkvirtualenv TotalDepth
$ cd TotalDepth/
$ python setup.py develop
```

4. Create a branch for local development:

```
$ git checkout -b name-of-your-bugfix-or-feature
```

Now you can make your changes locally.

5. When you’re done making changes, check that your changes pass flake8 and the tests, including testing other Python versions with tox:

```
$ flake8 TotalDepth tests
$ python setup.py test or py.test
$ tox
```

To get flake8 and tox, just pip install them into your virtualenv.

6. Commit your changes and push your branch to GitHub:

```
$ git add .
$ git commit -m "Your detailed description of your changes."
$ git push origin name-of-your-bugfix-or-feature
```

7. Submit a pull request through the GitHub website.

1.16.3 Pull Request Guidelines

Before you submit a pull request, check that it meets these guidelines:

1. The pull request should include tests.
2. If the pull request adds functionality, the docs should be updated. Put your new functionality into a function with a docstring, and add the feature to the list in README.rst.
3. The pull request should work for Python 3.3 and above (we don't support Python 2.x), and for PyPy. Check https://travis-ci.org/paulross/TotalDepth/pull_requests and make sure that the tests pass for all supported Python versions.

1.16.4 Tips

To run a subset of tests:

```
$ pytest tests.test_TotalDepth
```

1.17 History

1.17.1 0.2.0 (2017-09-25)

- Moved to Github: <https://github.com/paulross/TotalDepth>
- First release on PyPI.

1.17.2 0.1.0 (2012-03-03)

- First release on Sourceforge: <https://sourceforge.net/projects/TotalDepth/> registered: 2011-10-02

Earlier versions (unreleased):

- OpenLis - 2010-11-11 to 2011-08-01
- PyLis - 2009 to 2010

1.18 TotalDepth

Petrophysical software capable of processing wireline logs.


- Free software: GPL 2.0

- Documentation: <https://TotalDepth.readthedocs.io>


1.18.1 Features

- Reads LIS, LAS (1.2, 2.0) file formats for analysis or conversion to other formats.
- Plots log data as SVG viewable in any modern browser.
- Plots can be made with a wide variety of plot formats.
- TotalDepth can generate HTML summaries of log data.
- TotalDepth is written in Python so it is fast to develop with.
- Special indexing techniques are used to be able to randomly access sequential files.

Here is an example of a LAS file plotted with the Tripple Combo plot format as seen in a browser, this includes the API header:



An example of a High Resolution Dipmeter plotted at 1:25 scale:



1.18.2 Credits

This package was created with [Cookiecutter](#) and the [audreyr/cookiecutter-pypackage](#) project template.
For many year this project was hosted by [Sourceforge](#). Thank you Sourceforge!

INDICES AND TABLES

- `genindex`
- `modindex`
- `search`

PYTHON MODULE INDEX

t

TotalDepth.LAS.core.LASRead, 116
TotalDepth.LIS.core.cRepCode, 72
TotalDepth.LIS.core.EngVal, 75
TotalDepth.LIS.core.File, 80
TotalDepth.LIS.core.FileIndexer, 96
TotalDepth.LIS.core.FrameSet, 106
TotalDepth.LIS.core.LogiRec, 87
TotalDepth.LIS.core.LogPass, 100
TotalDepth.LIS.core.Mnem, 77
TotalDepth.LIS.core.PhysRec, 84
TotalDepth.LIS.core.pRepCode, 70
TotalDepth.LIS.core.RawStream, 78
TotalDepth.LIS.core.RepCode, 68
TotalDepth.LIS.core.Rle, 111
TotalDepth.LIS.core.TifMarker, 81
TotalDepth.LIS.core.Type01Plan, 114
TotalDepth.LIS.core.Units, 73
TotalDepth.util.CmnCmdOpts, 119
TotalDepth.util.DictTree, 120
TotalDepth.util.DirWalk, 122
TotalDepth.util.ExecTimer, 122
TotalDepth.util.FileBuffer, 123
TotalDepth.util.Histogram, 124
TotalDepth.util.HtmlUtils, 125
TotalDepth.util.plot.AREACfg, 142
TotalDepth.util.plot.Coord, 130
TotalDepth.util.plot.FILMCfg, 146
TotalDepth.util.plot.FILMCfgXML, 152
TotalDepth.util.plot.LogHeader, 162
TotalDepth.util.plot.Plot, 164
TotalDepth.util.plot.PlotConstants, 136
TotalDepth.util.plot.PRESCfg, 153
TotalDepth.util.plot.PRESCfgXML, 161
TotalDepth.util.plot.Stroke, 133
TotalDepth.util.plot.SVGWriter, 133
TotalDepth.util.plot.Track, 137
TotalDepth.util.plot.XGrid, 140
TotalDepth.util.plot.XMLCf, 141
TotalDepth.util.plot.XMLMatches, 142
TotalDepth.util.XmlWrite, 126

Symbols

__add__() (TotalDepth.LIS.core.EngVal.EngVal method), 76
 __add__() (TotalDepth.util.plot.Coord.Dim method), 130
 __contains__() (TotalDepth.LAS.core.LASRead.LASSection method), 117
 __contains__() (TotalDepth.LIS.core.LogiRec.LrTable method), 93
 __contains__() (TotalDepth.LIS.core.LogiRec.TableRow method), 93
 __contains__() (TotalDepth.util.plot.FILMCfg.FilmCfg method), 151
 __contains__() (TotalDepth.util.plot.PRESCfg.PresCfg method), 160
 __enter__() (TotalDepth.LIS.core.RawStream.RawStream method), 79
 __enter__() (TotalDepth.util.XmlWrite.Element method), 128
 __enter__() (TotalDepth.util.XmlWrite.XmlStream method), 128
 __eq__() (TotalDepth.LIS.core.EngVal.EngVal method), 76
 __eq__() (TotalDepth.LIS.core.Mnem.Mnem method), 78
 __eq__() (TotalDepth.util.plot.Coord.Dim method), 130
 __eq__() (TotalDepth.util.plot.Coord.Pt method), 131
 __exit__() (TotalDepth.LIS.core.RawStream.RawStream method), 79
 __exit__() (TotalDepth.util.XmlWrite.Element method), 128
 __exit__() (TotalDepth.util.XmlWrite.XmlStream method), 128
 __ge__() (TotalDepth.LIS.core.EngVal.EngVal method), 76
 __ge__() (TotalDepth.util.plot.Coord.Dim method), 131
 __getattr__() (TotalDepth.LIS.core.LogiRec.EntryBlockSet method), 94
 __getitem__() (TotalDepth.LAS.core.LASRead.LASBase method), 118
 __getitem__() (TotalDepth.LAS.core.LASRead.LASSection method), 117
 __getitem__() (TotalDepth.LIS.core.LogiRec.EntryBlockSet method), 94
 __getitem__() (TotalDepth.LIS.core.LogiRec.LrTable method), 93
 __getitem__() (TotalDepth.LIS.core.LogiRec.TableRow method), 93
 __getitem__() (TotalDepth.LIS.core.Rle.RLE method), 112
 __getitem__() (TotalDepth.util.FileBuffer.FileBuffer method), 124
 __getitem__() (TotalDepth.util.Histogram.Histogram method), 124
 __getitem__() (TotalDepth.util.plot.FILMCfg.FilmCfg method), 151
 __getitem__() (TotalDepth.util.plot.FILMCfg.PhysFilmCfg method), 150
 __getitem__() (TotalDepth.util.plot.PRESCfg.PresCfg method), 160
 __getnewargs__() (TotalDepth.LAS.core.LASRead.SectLine method), 117
 __getnewargs__() (TotalDepth.util.DirWalk.FileInOut method), 122
 __getnewargs__() (TotalDepth.util.plot.PRESCfg.TrackWidthData method), 159
 __getnewargs__() (TotalDepth.util.plot.Plot.ScaleSliceCurve method), 166
 __gt__() (TotalDepth.LIS.core.EngVal.EngVal method), 76
 __gt__() (TotalDepth.util.plot.Coord.Dim method), 131
 __hash__() (TotalDepth.LIS.core.Mnem.Mnem method), 78
 __iadd__() (TotalDepth.LIS.core.EngVal.EngVal method), 76
 __iadd__() (TotalDepth.util.plot.Coord.Dim method), 130
 __imul__() (TotalDepth.LIS.core.EngVal.EngVal method), 76
 __init__() (TotalDepth.LAS.core.LASRead.LASRead method), 119
 __init__() (TotalDepth.LIS.core.LogiRec.CbEngValRead method), 92
 __init__() (TotalDepth.LIS.core.LogiRec.CbEngValWrite method), 92

`__init__()` (TotalDepth.LIS.core.LogiRec.LrBase method), 89
`__init__()` (TotalDepth.LIS.core.LogiRec.LrTable method), 93
`__init__()` (TotalDepth.LIS.core.LogiRec.LrTableWrite method), 94
`__init__()` (TotalDepth.LIS.core.Mnem.Mnem method), 78
`__init__()` (TotalDepth.LIS.core.RawStream.RawStream method), 79
`__init__()` (TotalDepth.LIS.core.Rle.RLE method), 112
`__init__()` (TotalDepth.util.ExecTimer.ExecTimerList method), 123
`__init__()` (TotalDepth.util.XmlWrite.XmlStream method), 127
`__init__()` (TotalDepth.util.plot.FILMCfg.FilmCfgLISRead method), 152
`__init__()` (TotalDepth.util.plot.FILMCfg.PhysFilmCfg method), 150
`__init__()` (TotalDepth.util.plot.FILMCfg.PhysFilmCfgLISRead method), 151
`__init__()` (TotalDepth.util.plot.FILMCfgXML.FilmCfgXMLRead method), 153
`__init__()` (TotalDepth.util.plot.PRESCfg.CurveCfg method), 160
`__init__()` (TotalDepth.util.plot.PRESCfg.LineTransBase method), 158
`__init__()` (TotalDepth.util.plot.PRESCfg.LineTransLin method), 159
`__init__()` (TotalDepth.util.plot.PRESCfg.LineTransLog10 method), 159
`__init__()` (TotalDepth.util.plot.PRESCfg.PresCfgLISRead method), 161
`__init__()` (TotalDepth.util.plot.PRESCfgXML.CurveCfgXMLRead method), 161
`__init__()` (TotalDepth.util.plot.PRESCfgXML.PresCfgXMLRead method), 162
`__init__()` (TotalDepth.util.plot.Plot.CurvePlotScaleSlotMap method), 166
`__init__()` (TotalDepth.util.plot.Plot.PlotRoll method), 168
`__init__()` (TotalDepth.util.plot.SVGWriter.SVGCircle method), 133
`__init__()` (TotalDepth.util.plot.SVGWriter.SVGElipse method), 133
`__init__()` (TotalDepth.util.plot.SVGWriter.SVGGroup method), 133
`__init__()` (TotalDepth.util.plot.SVGWriter.SVGLine method), 134
`__init__()` (TotalDepth.util.plot.SVGWriter.SVGPointList method), 134
`__init__()` (TotalDepth.util.plot.SVGWriter.SVGPolygon method), 134
`__init__()` (TotalDepth.util.plot.SVGWriter.SVGPolyline method), 134
`__init__()` (TotalDepth.util.plot.SVGWriter.SVGRect method), 135
`__init__()` (TotalDepth.util.plot.SVGWriter.SVGText method), 135
`__init__()` (TotalDepth.util.plot.XGrid.XGrid method), 141
`__isub__()` (TotalDepth.LIS.core.EngVal.EngVal method), 76
`__isub__()` (TotalDepth.util.plot.Coord.Dim method), 130
`__iter__()` (TotalDepth.LIS.core.Mnem.Mnem method), 78
`__itruediv__()` (TotalDepth.LIS.core.EngVal.EngVal method), 76
`__le__()` (TotalDepth.LIS.core.EngVal.EngVal method), 76
`__le__()` (TotalDepth.util.plot.Coord.Dim method), 130
`__len__()` (TotalDepth.LAS.core.LASRead.LASBase method), 118
`__len__()` (TotalDepth.LAS.core.LASRead.LASSection method), 117
`__len__()` (TotalDepth.LIS.core.LogiRec.LrTable method), 93
`__len__()` (TotalDepth.LIS.core.LogiRec.TableRow method), 93
`__len__()` (TotalDepth.LIS.core.Rle.RLE method), 112
`__len__()` (TotalDepth.util.DictTree.DictTree method), 120
`__len__()` (TotalDepth.util.ExecTimer.ExecTimerList method), 123
`__len__()` (TotalDepth.util.plot.FILMCfg.FilmCfg method), 151
`__len__()` (TotalDepth.util.plot.FILMCfg.PhysFilmCfg method), 150
`__len__()` (TotalDepth.util.plot.PRESCfg.PresCfg method), 160
`__lt__()` (TotalDepth.LIS.core.EngVal.EngVal method), 76
`__lt__()` (TotalDepth.LIS.core.Mnem.Mnem method), 78
`__lt__()` (TotalDepth.util.plot.Coord.Dim method), 130
`__lt__()` (TotalDepth.util.plot.Plot.CurvePlotScale method), 166
`__mul__()` (TotalDepth.LIS.core.EngVal.EngVal method), 76
`__ne__()` (TotalDepth.LIS.core.EngVal.EngVal method), 76
`__ne__()` (TotalDepth.LIS.core.Mnem.Mnem method), 78
`__ne__()` (TotalDepth.util.plot.Coord.Dim method), 131
`__new__()` (TotalDepth.LAS.core.LASRead.SectLine static method), 117
`__new__()` (TotalDepth.util.DirWalk.FileInOut static method), 122
`__new__()` (TotalDepth.util.plot.PRESCfg.TrackWidthData

- static method), 159
- __new__() (TotalDepth.util.plot.Plot.ScaleSliceCurve static method), 166
- __radd__() (TotalDepth.LIS.core.EngVal.EngVal method), 76
- __repr__() (TotalDepth.LAS.core.LASRead.SectLine method), 117
- __repr__() (TotalDepth.LIS.core.Mnem.Mnem method), 78
- __repr__() (TotalDepth.util.DirWalk.FileInOut method), 122
- __repr__() (TotalDepth.util.plot.PRESCfg.TrackWidthData method), 159
- __repr__() (TotalDepth.util.plot.Plot.ScaleSliceCurve method), 166
- __rmul__() (TotalDepth.LIS.core.EngVal.EngVal method), 76
- __rsub__() (TotalDepth.LIS.core.EngVal.EngVal method), 76
- __rtruediv__() (TotalDepth.LIS.core.EngVal.EngVal method), 77
- __str__() (TotalDepth.LIS.core.EngVal.EngVal method), 77
- __str__() (TotalDepth.LIS.core.EngVal.EngValRc method), 77
- __str__() (TotalDepth.LIS.core.LogiRec.LrBase method), 90
- __str__() (TotalDepth.LIS.core.Mnem.Mnem method), 78
- __str__() (TotalDepth.LIS.core.Rle.RLE method), 112
- __str__() (TotalDepth.LIS.core.Rle.RLEItem method), 112
- __str__() (TotalDepth.LIS.core.Rle.RLEItemType01 method), 113
- __str__() (TotalDepth.LIS.core.Rle.RLEType01 method), 114
- __str__() (TotalDepth.util.plot.Coord.Box method), 131
- __str__() (TotalDepth.util.plot.Coord.Margin method), 131
- __str__() (TotalDepth.util.plot.Coord.Pad method), 131
- __str__() (TotalDepth.util.plot.Coord.Pt method), 131
- __sub__() (TotalDepth.LIS.core.EngVal.EngVal method), 77
- __sub__() (TotalDepth.util.plot.Coord.Dim method), 130
- __truediv__() (TotalDepth.LIS.core.EngVal.EngVal method), 77
- __weakref__ (TotalDepth.LAS.core.LASRead.LASBase attribute), 119
- __weakref__ (TotalDepth.LAS.core.LASRead.LASSection attribute), 118
- __weakref__ (TotalDepth.LIS.core.EngVal.EngVal attribute), 77
- __weakref__ (TotalDepth.LIS.core.LogiRec.CbEngVal attribute), 92
- __weakref__ (TotalDepth.LIS.core.LogiRec.DatumSpecBlock attribute), 95
- __weakref__ (TotalDepth.LIS.core.LogiRec.EntryBlockSet attribute), 95
- __weakref__ (TotalDepth.LIS.core.LogiRec.LrBase attribute), 90
- __weakref__ (TotalDepth.LIS.core.LogiRec.LrFactory attribute), 96
- __weakref__ (TotalDepth.LIS.core.LogiRec.TableRow attribute), 93
- __weakref__ (TotalDepth.LIS.core.Mnem.Mnem attribute), 78
- __weakref__ (TotalDepth.LIS.core.RawStream.RawStream attribute), 79
- __weakref__ (TotalDepth.LIS.core.Rle.RLE attribute), 113
- __weakref__ (TotalDepth.LIS.core.Rle.RLEItem attribute), 112
- __weakref__ (TotalDepth.LIS.core.Type01Plan.FrameSetPlan attribute), 115
- __weakref__ (TotalDepth.util.DictTree.DictTree attribute), 120
- __weakref__ (TotalDepth.util.ExecTimer.ExecEvent attribute), 123
- __weakref__ (TotalDepth.util.ExecTimer.ExecTimerList attribute), 123
- __weakref__ (TotalDepth.util.FileBuffer.ExceptionFileBuffer attribute), 123
- __weakref__ (TotalDepth.util.FileBuffer.FileBuffer attribute), 124
- __weakref__ (TotalDepth.util.Histogram.Histogram attribute), 124
- __weakref__ (TotalDepth.util.XmlWrite.Element attribute), 128
- __weakref__ (TotalDepth.util.XmlWrite.XmlStream attribute), 128
- __weakref__ (TotalDepth.util.plot.FILMCfg.FilmCfg attribute), 151
- __weakref__ (TotalDepth.util.plot.FILMCfg.PhysFilmCfg attribute), 150
- __weakref__ (TotalDepth.util.plot.PRESCfg.CurveCfg attribute), 160
- __weakref__ (TotalDepth.util.plot.PRESCfg.LineTransBase attribute), 159
- __weakref__ (TotalDepth.util.plot.PRESCfg.PresCfg attribute), 160
- __weakref__ (TotalDepth.util.plot.Plot.CurvePlotScaleSlotMap attribute), 167
- __weakref__ (TotalDepth.util.plot.Plot.Plot attribute), 170
- __weakref__ (TotalDepth.util.plot.Plot.PlotRoll attribute), 169
- __weakref__ (TotalDepth.util.plot.XGrid.XGrid attribute), 141

A

AccActivity (class in TotalDepth.LIS.core.FrameSet), 111

AccBias (class in TotalDepth.LIS.core.FrameSet), 111

AccCount (class in TotalDepth.LIS.core.FrameSet), 110

AccDec (class in TotalDepth.LIS.core.FrameSet), 111

AccDelta (class in TotalDepth.LIS.core.FrameSet), 110

AccDrift (class in TotalDepth.LIS.core.FrameSet), 111

AccEq (class in TotalDepth.LIS.core.FrameSet), 110

AccInc (class in TotalDepth.LIS.core.FrameSet), 110

AccMax (class in TotalDepth.LIS.core.FrameSet), 110

AccMean (class in TotalDepth.LIS.core.FrameSet), 110

AccMin (class in TotalDepth.LIS.core.FrameSet), 109

AccStDev (class in TotalDepth.LIS.core.FrameSet), 110

accumulate() (TotalDepth.LIS.core.FrameSet.FrameSet method), 109

add() (TotalDepth.LIS.core.FileIndexer.IndexLogPass method), 97

add() (TotalDepth.LIS.core.FrameSet.AccActivity method), 111

add() (TotalDepth.LIS.core.FrameSet.AccBias method), 111

add() (TotalDepth.LIS.core.FrameSet.AccCount method), 110

add() (TotalDepth.LIS.core.FrameSet.AccDec method), 111

add() (TotalDepth.LIS.core.FrameSet.AccDelta method), 110

add() (TotalDepth.LIS.core.FrameSet.AccDrift method), 111

add() (TotalDepth.LIS.core.FrameSet.AccEq method), 110

add() (TotalDepth.LIS.core.FrameSet.AccInc method), 110

add() (TotalDepth.LIS.core.FrameSet.AccMax method), 110

add() (TotalDepth.LIS.core.FrameSet.AccMean method), 110

add() (TotalDepth.LIS.core.FrameSet.AccMin method), 110

add() (TotalDepth.LIS.core.FrameSet.AccStDev method), 110

add() (TotalDepth.LIS.core.Rle.RLE method), 113

add() (TotalDepth.LIS.core.Rle.RLEItem method), 112

add() (TotalDepth.LIS.core.Rle.RLEItemType01 method), 113

add() (TotalDepth.LIS.core.Rle.RLEType01 method), 114

add() (TotalDepth.util.DictTree.DictTree method), 120

add() (TotalDepth.util.Histogram.Histogram method), 124

add() (TotalDepth.util.plot.FILMCfg.FilmCfg method), 151

add() (TotalDepth.util.plot.PRESCfg.PresCfg method), 160

addCb() (TotalDepth.LIS.core.LogiRec.TableRow method), 93

addDatumBlock() (TotalDepth.LIS.core.LogiRec.LrTable method), 94

addMemberLine() (TotalDepth.LAS.core.LASRead.LASSection method), 117

addMemberLine() (TotalDepth.LAS.core.LASRead.LASSectionArray method), 118

addType01Data() (TotalDepth.LIS.core.LogPass.LogPass method), 100

addXMLRoot() (TotalDepth.util.plot.FILMCfgXML.FilmCfgXMLRead method), 153

APIHeaderBase (class in TotalDepth.util.plot.LogHeader), 163

APIHeaderLAS (class in TotalDepth.util.plot.LogHeader), 164

APIHeaderLIS (class in TotalDepth.util.plot.LogHeader), 163

argParser() (in module TotalDepth.util.CmnCmdOpts), 119

argParserIn() (in module TotalDepth.util.CmnCmdOpts), 119

argParserInOut() (in module TotalDepth.util.CmnCmdOpts), 119

assoc (TotalDepth.LAS.core.LASRead.SectLine attribute), 117

ATTR_MAP (TotalDepth.LIS.core.LogiRec.EntryBlockSet attribute), 94

availableWidth (TotalDepth.util.plot.Plot.PlotRoll attribute), 168

B

Backup Mode, 172

BACKUP_ALL (in module TotalDepth.util.plot.PRESCfg), 158

BACKUP_FROM_COUNT_MAP (in module TotalDepth.util.plot.PRESCfgXML), 161

BACKUP_FROM_MODE_MAP (in module TotalDepth.util.plot.PRESCfg), 158

BACKUP_FROM_MODE_MAP (in module TotalDepth.util.plot.PRESCfgXML), 161

BACKUP_LEFT (in module TotalDepth.util.plot.PRESCfg), 158

BACKUP_NONE (in module TotalDepth.util.plot.PRESCfg), 158

BACKUP_ONCE (in module TotalDepth.util.plot.PRESCfg), 158

BACKUP_RIGHT (in module TotalDepth.util.plot.PRESCfg), 158

BACKUP_TWICE (in module TotalDepth.util.plot.PRESCfg), 158

- BASE_UNITS (in module TotalDepth.util.plot.Coord), 130
- baseUnitsDim() (in module TotalDepth.util.plot.Coord), 131
- BLOCKS_TO_SKIP (TotalDepth.LIS.core.LogiRec.EntryBlockSet attribute), 94
- bool() (TotalDepth.util.plot.XMLCfg.LgXMLBase method), 142
- Box (class in TotalDepth.util.plot.Coord), 131
- bursts() (TotalDepth.LIS.core.LogiRec.DatumSpecBlock method), 95
- ## C
- canAdd() (TotalDepth.LIS.core.FileIndexer.IndexLogPass method), 97
- canAdd() (TotalDepth.LIS.core.FileIndexer.IndexObjBase method), 97
- canFit() (TotalDepth.util.plot.Plot.CurvePlotScaleSlotMap method), 166
- canPlotFromExternalRecords() (TotalDepth.LIS.core.FileIndexer.PlotRecordSet method), 98
- canPlotFromInternalRecords() (TotalDepth.LIS.core.FileIndexer.PlotRecordSet method), 99
- category() (in module TotalDepth.LIS.core.Units), 74
- categoryDescription() (in module TotalDepth.LIS.core.Units), 74
- CB_TYPES (TotalDepth.LIS.core.LogiRec.CbEngVal attribute), 92
- CbEngVal (class in TotalDepth.LIS.core.LogiRec), 92
- CbEngValRead (class in TotalDepth.LIS.core.LogiRec), 92
- CbEngValWrite (class in TotalDepth.LIS.core.LogiRec), 92
- channelSize() (TotalDepth.LIS.core.Type01Plan.FrameSetPlan method), 115
- characters() (TotalDepth.util.XmlWrite.XmlStream method), 127
- ChArTe (class in TotalDepth.LIS.core.FrameSet), 107
- chkIdx() (in module TotalDepth.LIS.core.FrameSet), 107
- chOffset() (TotalDepth.LIS.core.Type01Plan.FrameSetPlan method), 115
- chOutpMnemInFilmId() (TotalDepth.util.plot.FILMCfgXML.FilmCfgXMLRead method), 153
- close() (TotalDepth.LIS.core.File.FileWrite method), 81
- close() (TotalDepth.LIS.core.PhysRec.PhysRecBase method), 86
- close() (TotalDepth.LIS.core.PhysRec.PhysRecWrite method), 87
- close() (TotalDepth.LIS.core.RawStream.RawStream method), 79
- close() (TotalDepth.LIS.core.TifMarker.TifMarkerWrite method), 83
- coding (TotalDepth.util.plot.Stroke.Stroke attribute), 133
- colLabels() (TotalDepth.LIS.core.LogiRec.LrTable method), 93
- coloStroke() (in module TotalDepth.util.plot.PRESCfg), 158
- colour (TotalDepth.util.plot.Stroke.Stroke attribute), 133
- comment() (TotalDepth.util.XmlWrite.XmlStream method), 127
- COMMENTS_IN_SVG_SECTION (in module TotalDepth.util.plot.Plot), 166
- COMMENTS_IN_SVG_SECTION_LEVEL_TUPLE (in module TotalDepth.util.plot.Plot), 166
- COMMENTS_IN_SVG_SECTION_WIDTH (in module TotalDepth.util.plot.Plot), 166
- COMMENTS_IN_SVG_TRACE (in module TotalDepth.util.plot.Plot), 165
- COMPONENT_BLOCK_DATUM_BLOCK_ENTRY (in module TotalDepth.LIS.core.LogiRec), 92
- COMPONENT_BLOCK_DATUM_BLOCK_START (in module TotalDepth.LIS.core.LogiRec), 91
- COMPONENT_BLOCK_TABLE (in module TotalDepth.LIS.core.LogiRec), 91
- computeChecksum() (TotalDepth.LIS.core.PhysRec.PhysRecTail method), 87
- contFileName (TotalDepth.LIS.core.LogiRec.LrFileHeadTail attribute), 90
- convert() (in module TotalDepth.LIS.core.Units), 74
- convert() (in module TotalDepth.util.plot.Coord), 130
- convert() (TotalDepth.LIS.core.EngVal.EngVal method), 77
- convert() (TotalDepth.LIS.core.Units.UnitConvert method), 73
- convert() (TotalDepth.LIS.core.Units.UnitConvertCategory method), 74
- convert() (TotalDepth.util.plot.Coord.Dim method), 130
- convert() (TotalDepth.util.plot.Coord.Pt method), 131
- convertPt() (in module TotalDepth.util.plot.Coord), 132
- CURVE_LEGEND_FONT_FAMILY (TotalDepth.util.plot.Plot.Plot attribute), 169
- CURVE_LEGEND_FONT_SIZE (TotalDepth.util.plot.Plot.Plot attribute), 169
- CurveCfg (class in TotalDepth.util.plot.PRESCfg), 160
- CurveCfgXMLRead (class in TotalDepth.util.plot.PRESCfgXML), 161
- curveMnems() (TotalDepth.LAS.core.LASRead.LASBase method), 119
- curveName (TotalDepth.util.plot.Plot.ScaleSliceCurve attribute), 166
- CurvePlotScale (class in TotalDepth.util.plot.Plot), 166
- CurvePlotScaleSlotMap (class in TotalDepth.util.plot.Plot), 166

- curveUnits() (TotalDepth.LIS.core.LogPass.LogPass method), 101
- curveUnitsAsStr() (TotalDepth.LAS.core.LASRead.LASBase method), 119
- curveUnitsAsStr() (TotalDepth.LIS.core.LogPass.LogPass method), 101
- ## D
- d (TotalDepth.util.plot.LogHeader.Static attribute), 162
- Data Format Specification Record, 173
- DataSeqBase (class in TotalDepth.LIS.core.FrameSet), 107
- datum (TotalDepth.LIS.core.Rle.RLEItem attribute), 112
- Datum Specification Block, 173
- DatumSpecBlock (class in TotalDepth.LIS.core.LogiRec), 95
- DatumSpecBlockRead (class in TotalDepth.LIS.core.LogiRec), 95
- DEBUG_LINE_BY_LINE (in module TotalDepth.LAS.core.LASRead), 116
- decodeString() (in module TotalDepth.util.XmlWrite), 127
- DEFAULT_HLINE_WIDTH_PX (in module TotalDepth.util.plot.PRESCfg), 158
- DEFAULT_INTERVAL_MAP (TotalDepth.util.plot.XGrid.XGrid attribute), 141
- DEFAULT_INTERVAL_TEXT (TotalDepth.util.plot.XGrid.XGrid attribute), 141
- DEFAULT_LLINE_WIDTH_PX (in module TotalDepth.util.plot.PRESCfg), 158
- DEFAULT_PLOT_LIS_UNITS (in module TotalDepth.util.plot.PlotConstants), 136
- DEFAULT_PLOT_UNITS (in module TotalDepth.util.plot.PlotConstants), 136
- DEFAULT_VALUE_FORMAT (in module TotalDepth.util.plot.SVGWriter), 133
- DEFAULT_VALUE_FORMAT_POINTS (in module TotalDepth.util.plot.SVGWriter), 133
- depth (TotalDepth.util.plot.Plot.PlotRoll attribute), 168
- depth() (TotalDepth.util.DictTree.DictTree method), 120
- DEPTH_PER_CH (TotalDepth.util.plot.Track.Track attribute), 140
- depthDim (TotalDepth.util.plot.Plot.PlotRoll attribute), 168
- desc (TotalDepth.LAS.core.LASRead.SectLine attribute), 117
- desc (TotalDepth.LIS.core.LogiRec.LrBase attribute), 90
- description() (TotalDepth.util.plot.FILMCfgXML.FilmCfgXML method), 153
- DFSR, 173
- dfsr (TotalDepth.LIS.core.LogPass.LogPass attribute), 101
- DictTree (class in TotalDepth.util.DictTree), 120
- DictTreeHtmlTable (class in TotalDepth.util.DictTree), 120
- Dim (class in TotalDepth.util.plot.Coord), 130
- dimensionless() (TotalDepth.LIS.core.EngVal.EngVal method), 77
- dimIn() (in module TotalDepth.util.plot.Coord), 131
- dimToTxt() (in module TotalDepth.util.plot.SVGWriter), 135
- dipmeterIndex() (TotalDepth.LIS.core.FrameSet.ChArTe method), 107
- dirWalk() (in module TotalDepth.util.DirWalk), 122
- divide() (TotalDepth.util.plot.Coord.Dim method), 130
- DLIS, 173
- DSB, 173
- DSCA_MAP (TotalDepth.util.plot.FILMCfg.PhysFilmCfgLISRead attribute), 151
- dumpFrames() (TotalDepth.LIS.core.FrameSet.FrameSet method), 108
- ## E
- EB_DOC (TotalDepth.LIS.core.LogiRec.EntryBlockSet attribute), 94
- EFLR, 173
- Element (class in TotalDepth.util.XmlWrite), 128
- encode() (TotalDepth.LIS.core.EngVal.EngValRc method), 77
- encodeString() (in module TotalDepth.util.XmlWrite), 126
- endElement() (TotalDepth.util.XmlWrite.XmlStream method), 128
- Engineering Value, 173
- EngVal (class in TotalDepth.LIS.core.EngVal), 76
- EngValRc (class in TotalDepth.LIS.core.EngVal), 77
- Entry Block, 173
- EntryBlockRead (class in TotalDepth.LIS.core.LogiRec), 94
- EntryBlockSet (class in TotalDepth.LIS.core.LogiRec), 94
- eof (TotalDepth.LIS.core.TifMarker.TifMarkerBase attribute), 83
- EVENT_EXTRAPOLATE (in module TotalDepth.LIS.core.LogPass), 100
- EVENT_EXTRAPOLATE (in module TotalDepth.LIS.core.Type01Plan), 114
- EVENT_READ (in module TotalDepth.LIS.core.LogPass), 100
- EVENT_READ (in module TotalDepth.LIS.core.Type01Plan), 114
- EVENT_SEEK_LR (in module TotalDepth.LIS.core.LogPass), 100
- EVENT_SKIP (in module TotalDepth.LIS.core.LogPass), 100

- EVENT_SKIP (in module totalDepth.LIS.core.Type01Plan), 114
- ExceptionCbEngValInit, 92
- ExceptionCbWrite, 87
- ExceptionCoord, 130
- ExceptionCoordUnitConvert, 130
- ExceptionCurveCfg, 157
- ExceptionCurveCfgCtor, 158
- ExceptionCurveCfgLISRead, 158
- ExceptionCurveCfgXMLRead, 161
- ExceptionDatumSpecBlock, 95
- ExceptionDictTree, 120
- ExceptionDirWalk, 122
- ExceptionEntryBlock, 94
- ExceptionEntryBlockSetInit, 94
- ExceptionExecTimer, 122
- ExceptionFile, 80
- ExceptionFileBuffer, 123
- ExceptionFileBufferEOF, 124
- ExceptionFileIndex, 96
- ExceptionFileRead, 80
- ExceptionFileWrite, 80
- ExceptionFILMCfg, 150
- ExceptionFilmCfgLISRead, 150
- ExceptionFILMCfgXML, 152
- ExceptionFILMCfgXMLRead, 152
- ExceptionFILMCfgXMLReadLookUp, 152
- ExceptionFrameSet, 106
- ExceptionFrameSetEmpty, 107
- ExceptionFrameSetMixedChannels, 107
- ExceptionFrameSetNULLSpacing, 107
- ExceptionFrameSetPlan, 114
- ExceptionFrameSetPlanNegLen, 114
- ExceptionFrameSetPlanOverrun, 114
- ExceptionLASKeyError, 116
- ExceptionLASRead, 116
- ExceptionLASReadData, 116
- ExceptionLASReadSection, 116
- ExceptionLASReadSectionArray, 116
- ExceptionLineTransBase, 157
- ExceptionLineTransBaseMath, 157
- ExceptionLogHeader, 162
- ExceptionLogHeaderLAS, 162
- ExceptionLogHeaderLIS, 162
- ExceptionLogPass, 100
- ExceptionLogPassCtor, 100
- ExceptionLogPassKeyError, 100
- ExceptionLogPassNoFrameSet, 100
- ExceptionLogPassNoType01Data, 100
- ExceptionLr, 87
- ExceptionLrNotImplemented, 87
- ExceptionLrTable, 92
- ExceptionLrTableCompose, 92
- ExceptionLrTableInit, 92
- ExceptionLrTableInternalStructuresCorrupt, 92
- ExceptionLrTableRow, 92
- ExceptionLrTableRowInit, 92
- ExceptionPhysFilmCfg, 150
- ExceptionPhysRec, 84
- ExceptionPhysRecEOF, 84
- ExceptionPhysRecTail, 84
- ExceptionPhysRecUndefinedChecksum, 84
- ExceptionPhysRecUnknownType, 84
- ExceptionPhysRecWrite, 84
- ExceptionPlotXGrid, 141
- ExceptionPRESCfg, 157
- ExceptionPresCfg, 157
- ExceptionPRESCfgLISRead, 157
- ExceptionPRESCfgXML, 161
- ExceptionPresCfgXMLRead, 161
- ExceptionRawStream, 78
- ExceptionRawStreamEOF, 78
- ExceptionRepCode, 70
- ExceptionRepCodeNoLength, 68
- ExceptionRepCodeRead, 69
- ExceptionRepCodeUnknown, 70
- ExceptionRepCodeWrite, 69
- ExceptionSVGWriter, 133
- ExceptionTifMarker, 82
- ExceptionTotalDepthLISPlot, 166
- ExceptionTotalDepthLISPlotTrack, 139
- ExceptionTotalDepthPlotRoll, 166
- ExceptionUnits, 73
- ExceptionUnitsMismatchedCategory, 73
- ExceptionUnitsNoUnitInCategory, 73
- ExceptionUnitsUnknownCategory, 73
- ExceptionUnitsUnknownUnit, 73
- ExceptionXml, 126
- ExceptionXMLCfg, 141
- ExceptionXMLCfgMissingElem, 141
- ExceptionXMLCfgNoContent, 141
- ExceptionXMLCfgWrongRootElem, 141
- ExceptionXmlEndElement, 126
- ExecEvent (class in TotalDepth.util.ExecTimer), 122
- ExecTimerList (class in TotalDepth.util.ExecTimer), 123
- Explicitly Formatted Logical Record, 173
- extFrameNum() (TotalDepth.LIS.core.FrameSet.FrameSet method), 108
- ## F
- FileBase (class in TotalDepth.LIS.core.File), 80
- FileBuffer (class in TotalDepth.util.FileBuffer), 124
- fileCurveMap() (in module TotalDepth.util.plot.XMLMatches), 142
- fileCurveMapFromFILM() (in module TotalDepth.util.plot.XMLMatches), 142
- FileIndex (class in TotalDepth.LIS.core.FileIndexer), 96
- FileInOut (class in TotalDepth.util.DirWalk), 122

filePathIn (TotalDepth.util.DirWalk.FileInOut attribute), [122](#)
filePathOut (TotalDepth.util.DirWalk.FileInOut attribute), [122](#)
FileRead (class in TotalDepth.LIS.core.File), [80](#)
FileWrite (class in TotalDepth.LIS.core.File), [81](#)
FilmCfg (class in TotalDepth.util.plot.FILMCfg), [151](#)
FilmCfgLISRead (class in TotalDepth.util.plot.FILMCfg), [152](#)
FilmCfgXMLRead (class in TotalDepth.util.plot.FILMCfgXML), [153](#)
filmIdS() (TotalDepth.util.plot.Plot.Plot method), [170](#)
finalise() (TotalDepth.LAS.core.LASRead.LASSection method), [117](#)
finalise() (TotalDepth.LAS.core.LASRead.LASSectionArray method), [118](#)
find() (TotalDepth.LAS.core.LASRead.LASSection method), [118](#)
first() (TotalDepth.LIS.core.Rle.RLE method), [113](#)
first() (TotalDepth.LIS.core.Rle.RLEItem method), [112](#)
fit() (TotalDepth.util.plot.Plot.CurvePlotScaleSlotMap method), [167](#)
float() (TotalDepth.util.plot.XMLCfG.LgXMLBase method), [142](#)
font (TotalDepth.util.plot.LogHeader.Static attribute), [162](#)
FONT_PROP (in module TotalDepth.util.plot.LogHeader), [163](#)
format (TotalDepth.LAS.core.LASRead.SectLine attribute), [117](#)
Frame, [173](#)
Frame Set, [173](#)
frame() (TotalDepth.LIS.core.FrameSet.FrameSet method), [108](#)
frameFromX() (TotalDepth.LIS.core.LogPass.LogPass method), [101](#)
frames (TotalDepth.LIS.core.FrameSet.FrameSet attribute), [108](#)
FrameSet (class in TotalDepth.LIS.core.FrameSet), [107](#)
frameSet (TotalDepth.LIS.core.LogPass.LogPass attribute), [101](#)
frameSetLongStr() (TotalDepth.LIS.core.LogPass.LogPass method), [101](#)
FrameSetPlan (class in TotalDepth.LIS.core.Type01Plan), [114](#)
frameSize (TotalDepth.LIS.core.Type01Plan.FrameSetPlan attribute), [115](#)
frameSize() (TotalDepth.LAS.core.LASRead.LASSectionArray method), [118](#)
frameSpacing() (TotalDepth.LIS.core.Rle.RLEType01 method), [114](#)
frameView() (TotalDepth.LIS.core.FrameSet.FrameSet method), [109](#)
from49() (in module TotalDepth.LIS.core.pRepCode), [70](#)
from50() (in module TotalDepth.LIS.core.pRepCode), [70](#)
from56() (in module TotalDepth.LIS.core.pRepCode), [70](#)
from66() (in module TotalDepth.LIS.core.pRepCode), [70](#)
from68() (in module TotalDepth.LIS.core.pRepCode), [71](#)
from70() (in module TotalDepth.LIS.core.pRepCode), [71](#)
from73() (in module TotalDepth.LIS.core.pRepCode), [71](#)
from77() (in module TotalDepth.LIS.core.pRepCode), [71](#)
from79() (in module TotalDepth.LIS.core.pRepCode), [71](#)

G

genAll() (TotalDepth.LIS.core.FileIndexer.FileIndex method), [96](#)
genAll() (TotalDepth.LIS.core.FrameSet.FrameSet method), [109](#)
genBigFirst() (in module TotalDepth.util.DirWalk), [122](#)
genCells() (TotalDepth.LIS.core.LogiRec.TableRow method), [92](#)
genChScPoints() (TotalDepth.LIS.core.FrameSet.FrameSet method), [109](#)
genChScValues() (TotalDepth.LIS.core.FrameSet.FrameSet method), [109](#)
genColRowEvents() (TotalDepth.util.DictTree.DictTreeHtmlTable method), [122](#)
genEvents() (TotalDepth.LIS.core.Type01Plan.FrameSetPlan method), [115](#)
genEventsUnits() (TotalDepth.util.plot.XGrid.XGrid method), [141](#)
genExtChIndexes() (TotalDepth.LIS.core.FrameSet.FrameSet method), [109](#)
genFrameSetHeadings() (TotalDepth.LIS.core.LogPass.LogPass method), [101](#)
genFrameSetScNameUnit() (TotalDepth.LIS.core.LogPass.LogPass method), [101](#)
genLd() (TotalDepth.LIS.core.PhysRec.PhysRecRead method), [86](#)
genLinear10() (in module TotalDepth.util.plot.Track), [140](#)
genLines() (in module TotalDepth.LAS.core.LASRead), [116](#)
genLisBytes() (TotalDepth.LIS.core.LogiRec.LrTable method), [94](#)
genLog10() (in module TotalDepth.util.plot.Track), [140](#)
genLog10Decade1Start2 (in module TotalDepth.util.plot.Track), [140](#)
genLog10Decade2 (in module TotalDepth.util.plot.Track), [140](#)
genLog10Decade2Start2 (in module TotalDepth.util.plot.Track), [140](#)

genLog10Decade3 (in module TotalDepth.util.plot.Track), 140
 genLog10Decade4 (in module TotalDepth.util.plot.Track), 140
 genLog10Decade5 (in module TotalDepth.util.plot.Track), 140
 genLogPasses() (TotalDepth.LIS.core.FileIndexer.FileIndex method), 96
 genMultipleChScPoints() (TotalDepth.LIS.core.FrameSet.FrameSet method), 109
 genOffsets() (TotalDepth.LIS.core.Type01Plan.FrameSetPlan method), 115
 genOutpPoints() (TotalDepth.LAS.core.LASRead.LASBase method), 119
 genOutpPoints() (TotalDepth.LIS.core.LogPass.LogPass method), 101
 genPlotRecords() (TotalDepth.LIS.core.FileIndexer.FileIndex method), 96
 genRowNames() (TotalDepth.LIS.core.LogiRec.LrTable method), 93
 genRows() (TotalDepth.LIS.core.LogiRec.LrTable method), 93
 genRowValuesInColOrder() (TotalDepth.LIS.core.LogiRec.LrTable method), 94
 genScaleSliceCurve() (TotalDepth.util.plot.Plot.CurvePlotScaleSlotMap method), 167
 genSects() (TotalDepth.LAS.core.LASRead.LASBase method), 118
 genTracks() (TotalDepth.util.plot.FILMCfg.PhysFilmCfg method), 150
 genXAxisRange() (TotalDepth.util.plot.XGrid.XGrid method), 141
 genXAxisTextRange() (TotalDepth.util.plot.XGrid.XGrid method), 141
 genXPosStroke() (TotalDepth.util.plot.XGrid.XGrid method), 141
 getAllWsdMnemonics() (TotalDepth.LAS.core.LASRead.LASBase method), 119
 getInUnits() (TotalDepth.LIS.core.EngVal.EngVal method), 77
 getWsdMnem() (TotalDepth.LAS.core.LASRead.LASBase method), 119

H

halfTracks (TotalDepth.util.plot.PRESCfg.TrackWidthData attribute), 159
 halfTrackStart (TotalDepth.util.plot.PRESCfg.TrackWidthData attribute), 159

hasActiveTimer (TotalDepth.util.ExecTimer.ExecTimerList attribute), 123
 hasCompleted (TotalDepth.util.ExecTimer.ExecEvent attribute), 123
 hasCurvesForDest() (TotalDepth.util.plot.PRESCfg.PresCfg method), 160
 hasDataToPlotLAS() (TotalDepth.util.plot.Plot.Plot method), 170
 hasDataToPlotLIS() (TotalDepth.util.plot.Plot.Plot method), 170
 hasGrid (TotalDepth.util.plot.Track.Track attribute), 140
 hasLASExtension() (in module TotalDepth.LAS.core.LASRead), 116
 hasLd() (TotalDepth.LIS.core.File.FileRead method), 80
 hasLd() (TotalDepth.LIS.core.PhysRec.PhysRecRead method), 86
 hasOutpMnem() (TotalDepth.LAS.core.LASRead.LASBase method), 119
 hasOutpMnem() (TotalDepth.LIS.core.LogPass.LogPass method), 101
 hasPrevious (TotalDepth.LIS.core.TifMarker.TifMarkerRead attribute), 83
 hasTail() (TotalDepth.LIS.core.PhysRec.PhysRecTail method), 86
 hasUnit() (in module TotalDepth.LIS.core.Units), 74
 hasUnitCategory() (in module TotalDepth.LIS.core.Units), 74
 hasXAxisData (TotalDepth.LIS.core.Rle.RLEType01 attribute), 114
 HEADER_PLOT_UNITS (in module TotalDepth.util.plot.LogHeader), 163
 Histogram (class in TotalDepth.util.Histogram), 124

id (TotalDepth.util.XmlWrite.XmlStream attribute), 127
 IFLR, 173
 iflrType (TotalDepth.LIS.core.LogPass.LogPass attribute), 101
 iflrType() (TotalDepth.LIS.core.FileIndexer.IndexLogPass method), 97
 iflrType() (TotalDepth.LIS.core.FileIndexer.IndexObjBase method), 97
 index() (TotalDepth.LIS.core.FrameSet.ChArTe method), 107
 index() (TotalDepth.LIS.core.FrameSet.SuChArTe method), 107
 IndexFileHead (class in TotalDepth.LIS.core.FileIndexer), 96
 IndexFileHeadTail (class in TotalDepth.LIS.core.FileIndexer), 96
 IndexFileTail (class in TotalDepth.LIS.core.FileIndexer), 97

- IndexLogPass (class in TotalDepth.LIS.core.FileIndexer), 97
- IndexLrFull (class in TotalDepth.LIS.core.FileIndexer), 97
- IndexNone (class in TotalDepth.LIS.core.FileIndexer), 97
- IndexObjBase (class in TotalDepth.LIS.core.FileIndexer), 97
- IndexReelHead (class in TotalDepth.LIS.core.FileIndexer), 98
- IndexReelHeadTail (class in TotalDepth.LIS.core.FileIndexer), 98
- IndexReelTail (class in TotalDepth.LIS.core.FileIndexer), 98
- IndexTable (class in TotalDepth.LIS.core.FileIndexer), 98
- IndexTapeHead (class in TotalDepth.LIS.core.FileIndexer), 98
- IndexTapeHeadTail (class in TotalDepth.LIS.core.FileIndexer), 98
- IndexTapeTail (class in TotalDepth.LIS.core.FileIndexer), 98
- IndexUnknownInternalFormat (class in TotalDepth.LIS.core.FileIndexer), 98
- Indirectly Formatted Logical Record, 173
- indirectSize (TotalDepth.LIS.core.Type01Plan.FrameSetPlan attribute), 114
- init() (TotalDepth.LIS.core.LogiRec.LrBase method), 89
- int() (TotalDepth.util.plot.XMLCfmg.LgXMLBase method), 142
- internalChIdx() (TotalDepth.LIS.core.FrameSet.FrameSet method), 109
- interpretTrac() (TotalDepth.util.plot.FILMCfmg.FilmCfmg method), 151
- interpretTrac() (TotalDepth.util.plot.FILMCfmg.PhysFilmCfmg method), 150
- interpretTrac() (TotalDepth.util.plot.FILMCfmgXML.PhysFilmCfmgXML method), 152
- intFrameNum() (TotalDepth.LIS.core.FrameSet.FrameSet method), 108
- isDelimiter (TotalDepth.LIS.core.FileIndexer.IndexObjBase attribute), 97
- isDelimiter() (in module TotalDepth.LIS.core.LogiRec), 89
- isEOF (TotalDepth.LIS.core.File.FileRead attribute), 81
- isIndirectX (TotalDepth.LIS.core.FrameSet.FrameSet attribute), 108
- isIndirectX (TotalDepth.LIS.core.LogPass.LogPass attribute), 101
- isInt() (in module TotalDepth.LIS.core.pRepCode), 71
- isNull (TotalDepth.LIS.core.LogiRec.DatumSpecBlock attribute), 95
- isOffScaleLeft() (TotalDepth.util.plot.PRESCfmg.LineTransBase method), 159
- isOffScaleRight() (TotalDepth.util.plot.PRESCfmg.LineTransBase method), 159
- isSingleParam (TotalDepth.LIS.core.LogiRec.LrTable attribute), 93
- ## J
- jsonObject() (TotalDepth.LIS.core.FileIndexer.FileIndex method), 96
- jsonObject() (TotalDepth.LIS.core.FileIndexer.IndexLogPass method), 97
- jsonObject() (TotalDepth.LIS.core.FileIndexer.IndexObjBase method), 97
- jsonObject() (TotalDepth.LIS.core.FileIndexer.IndexTable method), 98
- jsonObject() (TotalDepth.LIS.core.LogPass.LogPass method), 101
- ## K
- keys() (TotalDepth.LAS.core.LASRead.LASSection method), 118
- keys() (TotalDepth.util.DictTree.DictTree method), 120
- keys() (TotalDepth.util.plot.FILMCfmg.FilmCfmg method), 151
- keys() (TotalDepth.util.plot.PRESCfmg.PresCfmg method), 160
- ## L
- L2P() (TotalDepth.util.plot.PRESCfmg.LineTransBase method), 158
- L2P() (TotalDepth.util.plot.PRESCfmg.LineTransLin method), 159
- L2P() (TotalDepth.util.plot.PRESCfmg.LineTransLog10 method), 159
- LAS_FILE_EXT (in module TotalDepth.LAS.core.LASRead), 116
- LAS_FILE_EXT_LOWER (in module TotalDepth.LAS.core.LASRead), 116
- LASBase (class in TotalDepth.LAS.core.LASRead), 118
- LASRead (class in TotalDepth.LAS.core.LASRead), 119
- LASSection (class in TotalDepth.LAS.core.LASRead), 117
- LASSectionArray (class in TotalDepth.LAS.core.LASRead), 118
- last() (TotalDepth.LIS.core.Rle.RLE method), 113
- last() (TotalDepth.LIS.core.Rle.RLEItem method), 112
- ldIndex() (TotalDepth.LIS.core.File.FileRead method), 80
- ldRemaingInPr() (TotalDepth.LIS.core.PhysRec.PhysRecRead method), 86
- left (TotalDepth.util.plot.Track.Track attribute), 140
- leftL (TotalDepth.util.plot.PRESCfmg.LineTransBase attribute), 158
- leftP (TotalDepth.util.plot.PRESCfmg.TrackWidthData attribute), 160
- LEGEND_ARROW_DEPTH (TotalDepth.util.plot.Plot.Plot attribute), 169

LEGEND_ARROW_DISPLAY (TotalDepth.util.plot.Plot.Plot attribute), 169
LEGEND_ARROW_WIDTH (TotalDepth.util.plot.Plot.Plot attribute), 169
LEGEND_ARROW_WIDTH_PX (TotalDepth.util.plot.Plot.Plot attribute), 169
LEGEND_DEPTH_PER_CURVE (TotalDepth.util.plot.Plot.Plot attribute), 169
LEGEND_DEPTH_SPARE (TotalDepth.util.plot.Plot.Plot attribute), 169
LEGEND_HORIZONTAL_LINE_DEPTH_PROPORTION (TotalDepth.util.plot.Plot.Plot attribute), 169
LEN_MNEM (in module TotalDepth.LIS.core.Mnem), 78
lenDesc() (TotalDepth.util.ExecTimer.ExecEvent method), 123
LgXMLBase (class in TotalDepth.util.plot.XMLCfg), 142
LineTransBase (class in TotalDepth.util.plot.PRESCfg), 158
LineTransLin (class in TotalDepth.util.plot.PRESCfg), 159
LineTransLog10 (class in TotalDepth.util.plot.PRESCfg), 159
LIS, 173
LIS-79, 173
LIS-A, 173
LIS_CODI_MAP (in module TotalDepth.util.plot.PRESCfg), 158
LIS_COLO_MAP (in module TotalDepth.util.plot.PRESCfg), 158
LIS_MNEM_TO_LAS_MNEM (TotalDepth.util.plot.LogHeader.APIHeaderLAS attribute), 164
lisByteList() (TotalDepth.LIS.core.LogiRec.EntryBlockSet method), 95
lisBytes() (TotalDepth.LIS.core.LogiRec.CbEngVal method), 92
lisBytes() (TotalDepth.LIS.core.LogiRec.EntryBlockSet method), 95
lisColo() (in module TotalDepth.util.plot.PRESCfg), 158
lisSize (TotalDepth.LIS.core.FrameSet.ChArTe attribute), 107
lisSize (TotalDepth.LIS.core.FrameSet.FrameSet attribute), 108
lisSize() (in module TotalDepth.LIS.core.pRepCode), 71
lisSize() (TotalDepth.LIS.core.LogiRec.EntryBlockSet method), 95
literal() (TotalDepth.util.XmlWrite.XmlStream method), 127
Log Pass, 173
logDown (TotalDepth.LIS.core.LogiRec.EntryBlockSet attribute), 94
logDown() (TotalDepth.LAS.core.LASRead.LASBase method), 118
Logical Record, 173
Logical Record header, 173
logicalRecord (TotalDepth.LIS.core.FileIndexer.IndexObjBase attribute), 97
LogPass (class in TotalDepth.LIS.core.LogPass), 100
logPass (TotalDepth.LIS.core.FileIndexer.IndexLogPass attribute), 97
logUp (TotalDepth.LIS.core.LogiRec.EntryBlockSet attribute), 94
longDesc() (TotalDepth.LIS.core.FileIndexer.FileIndex method), 96
longStr() (TotalDepth.LIS.core.FrameSet.FrameSet method), 108
longStr() (TotalDepth.LIS.core.LogPass.LogPass method), 101
longStr() (TotalDepth.util.plot.FILMCfgXML.FilmCfgXMLRead method), 153
longStr() (TotalDepth.util.plot.PRESCfg.CurveCfg method), 160
LR_DESCRIPTION_MAP (in module TotalDepth.LIS.core.LogiRec), 89
LR_DESCRIPTION_UNKNOWN (in module TotalDepth.LIS.core.LogiRec), 89
LR_TYPE_ALL (in module TotalDepth.LIS.core.LogiRec), 89
LR_TYPE_ALTERNATE_DATA (in module TotalDepth.LIS.core.LogiRec), 87
LR_TYPE_BLANK_RECORD (in module TotalDepth.LIS.core.LogiRec), 88
LR_TYPE_BOOTSTRAP_LOADER (in module TotalDepth.LIS.core.LogiRec), 87
LR_TYPE_BOT (in module TotalDepth.LIS.core.LogiRec), 88
LR_TYPE_CP_KERNEL (in module TotalDepth.LIS.core.LogiRec), 88
LR_TYPE_DATA_DESCRIPTOR (in module TotalDepth.LIS.core.LogiRec), 87
LR_TYPE_DATA_FORMAT (in module TotalDepth.LIS.core.LogiRec), 87
LR_TYPE_DELIMITER (in module TotalDepth.LIS.core.LogiRec), 89
LR_TYPE_DELIMITER_END (in module TotalDepth.LIS.core.LogiRec), 89
LR_TYPE_DELIMITER_MARKER (in module TotalDepth.LIS.core.LogiRec), 89
LR_TYPE_DELIMITER_START (in module TotalDepth.LIS.core.LogiRec), 89
LR_TYPE_ENCRYPTED_TABLE (in module TotalDepth.LIS.core.LogiRec), 87
LR_TYPE_EOF (in module TotalDepth.LIS.core.LogiRec), 88
LR_TYPE_EOM (in module TotalDepth.LIS.core.LogiRec), 88

LR_TYPE_EOT (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_FILE_HEAD (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_FILE_TAIL (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_FLIC_COMMENT (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_IMAGE (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_JOB_ID (in module talDepth.LIS.core.LogiRec), 87

LR_TYPE_LOG_DATA (in module talDepth.LIS.core.LogiRec), 89

LR_TYPE_MARKER (in module talDepth.LIS.core.LogiRec), 89

LR_TYPE_NORMAL_DATA (in module talDepth.LIS.core.LogiRec), 87

LR_TYPE_OPERATOR_INPUT (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_OPERATOR_RESPONSE (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_PICTURE (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_PROGRAM_FILE_HEAD (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_PROGRAM_OVER_HEAD (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_PROGRAM_OVER_LOAD (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_REEL_HEAD (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_REEL_TAIL (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_SYSTEM_OUTPUT (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_TABLE_DATA (in module talDepth.LIS.core.LogiRec), 89

LR_TYPE_TABLE_DUMP (in module talDepth.LIS.core.LogiRec), 87

LR_TYPE_TAPE_HEAD (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_TAPE_TAIL (in module talDepth.LIS.core.LogiRec), 88

LR_TYPE_TOOL_INFO (in module talDepth.LIS.core.LogiRec), 87

LR_TYPE_TU10_BOOT (in module talDepth.LIS.core.LogiRec), 87

LR_TYPE_UNKNOWN_INTERNAL_FORMAT (in module TotalDepth.LIS.core.LogiRec), 89

LR_TYPE_WELL_DATA (in module talDepth.LIS.core.LogiRec), 87

LrBase (class in TotalDepth.LIS.core.LogiRec), 89

LrBOT (class in TotalDepth.LIS.core.LogiRec), 90

To- LrBOTRead (class in TotalDepth.LIS.core.LogiRec), 90

To- LrDataCount() (TotalDepth.util.plot.LogHeader.APIHeaderLIS method), 164

To- LrDFSR (class in TotalDepth.LIS.core.LogiRec), 95

To- LrDFSRRead (class in TotalDepth.LIS.core.LogiRec), 95

To- LrEOF (class in TotalDepth.LIS.core.LogiRec), 90

To- LrEOFRead (class in TotalDepth.LIS.core.LogiRec), 90

To- LrEOM (class in TotalDepth.LIS.core.LogiRec), 90

To- LrEOMRead (class in TotalDepth.LIS.core.LogiRec), 90

To- LrEOT (class in TotalDepth.LIS.core.LogiRec), 90

To- LrEOTRead (class in TotalDepth.LIS.core.LogiRec), 90

To- LrFactory (class in TotalDepth.LIS.core.LogiRec), 96

To- LrFactoryRead (class in TotalDepth.LIS.core.LogiRec), 96

To- LrFileHead (class in TotalDepth.LIS.core.LogiRec), 90

To- LrFileHeadRead (class in TotalDepth.LIS.core.LogiRec), 90

To- LrFileHeadTail (class in TotalDepth.LIS.core.LogiRec), 90

To- LrFileTail (class in TotalDepth.LIS.core.LogiRec), 90

To- LrFileTailRead (class in TotalDepth.LIS.core.LogiRec), 91

To- LRH, 173

To- LrMarker (class in TotalDepth.LIS.core.LogiRec), 90

To- LrMisc (class in TotalDepth.LIS.core.LogiRec), 91

To- LrMiscRead (class in TotalDepth.LIS.core.LogiRec), 91

To- LrNormalAlternateData (class in TotalDepth.LIS.core.LogiRec), 95

To- LrNormalAlternateDataRead (class in TotalDepth.LIS.core.LogiRec), 95

To- LrReelHead (class in TotalDepth.LIS.core.LogiRec), 91

To- LrReelHeadRead (class in TotalDepth.LIS.core.LogiRec), 91

To- LrReelHeadTail (class in TotalDepth.LIS.core.LogiRec), 91

To- LrReelTail (class in TotalDepth.LIS.core.LogiRec), 91

To- LrReelTailRead (class in TotalDepth.LIS.core.LogiRec), 91

To- LrReelTapeHeadTail (class in TotalDepth.LIS.core.LogiRec), 91

To- LrTable (class in TotalDepth.LIS.core.LogiRec), 93

To- LrTableRead (class in TotalDepth.LIS.core.LogiRec), 94

To- LrTableWrite (class in TotalDepth.LIS.core.LogiRec), 94

To- LrTapeHead (class in TotalDepth.LIS.core.LogiRec), 91

To- LrTapeHeadRead (class in TotalDepth.LIS.core.LogiRec), 91

To- LrTapeHeadTail (class in TotalDepth.LIS.core.LogiRec), 91

To- LrTapeTail (class in TotalDepth.LIS.core.LogiRec), 91

To- LrTapeTailRead (class in TotalDepth.LIS.core.LogiRec), 91

To- LrType (TotalDepth.LIS.core.FileIndexer.IndexObjBase attribute), 98

LrTypeS (TotalDepth.LIS.core.FileIndexer.FileIndex attribute), 96
 LrWithDateField (class in TotalDepth.LIS.core.LogiRec), 90

M

m (TotalDepth.LIS.core.Mnem.Mnem attribute), 78
 mainPanePlotDepth (TotalDepth.util.plot.Plot.PlotRoll attribute), 168
 Margin (class in TotalDepth.util.plot.Coord), 131
 MarginQtrInch (in module TotalDepth.util.plot.PlotConstants), 136
 markers() (TotalDepth.LIS.core.TifMarker.TifMarkerBase method), 83
 MAX_BACKUP_TRACK_CROSSING_LINES (TotalDepth.util.plot.Plot.Plot attribute), 169
 maxValue() (in module TotalDepth.LIS.core.pRepCode), 71
 MICRO_MARGIN (TotalDepth.util.plot.Plot.Plot attribute), 169
 minMaxValue() (in module TotalDepth.LIS.core.pRepCode), 71
 minValue() (in module TotalDepth.LIS.core.pRepCode), 71
 missingFields() (TotalDepth.util.plot.LogHeader.APIHeaderBase method), 163
 missingFields() (TotalDepth.util.plot.LogHeader.APIHeaderLAS method), 164
 missingFields() (TotalDepth.util.plot.LogHeader.APIHeaderLIS method), 163
 Mnem, 173
 Mnem (class in TotalDepth.LIS.core.Mnem), 78
 mnem (TotalDepth.LAS.core.LASRead.SectLine attribute), 117
 mnem (TotalDepth.util.plot.LogHeader.Static attribute), 162
 Mnemonic, 173
 mnemS() (TotalDepth.LAS.core.LASRead.LASSection method), 117

N

name (TotalDepth.LIS.core.FileIndexer.IndexTable attribute), 98
 name (TotalDepth.util.plot.FILMCfg.PhysFilmCfg attribute), 150
 nameFromString() (in module TotalDepth.util.XmlWrite), 127
 nbytes (TotalDepth.LIS.core.FrameSet.FrameSet attribute), 108
 newEngValInOpticalUnits() (TotalDepth.LIS.core.EngVal.EngVal method), 77
 newEngValInUnits() (TotalDepth.LIS.core.EngVal.EngVal method),

77

newPt() (in module TotalDepth.util.plot.Coord), 131
 nextFileName (TotalDepth.LIS.core.LogiRec.LrFileTail attribute), 91
 nextReelName (TotalDepth.LIS.core.LogiRec.LrReelTail attribute), 91
 nextTapeName (TotalDepth.LIS.core.LogiRec.LrTapeTail attribute), 91
 nullValue (TotalDepth.LAS.core.LASRead.LASBase attribute), 118
 nullValue (TotalDepth.LIS.core.LogPass.LogPass attribute), 101
 numBursts() (TotalDepth.LIS.core.FrameSet.FrameSet method), 108
 numBytes (TotalDepth.LIS.core.LogPass.LogPass attribute), 101
 numChannels (TotalDepth.LIS.core.FrameSet.FrameSet attribute), 108
 numChannels (TotalDepth.LIS.core.Type01Plan.FrameSetPlan attribute), 115
 numDataPoints() (TotalDepth.LAS.core.LASRead.LASBase method), 118
 numFrames (TotalDepth.LIS.core.FrameSet.FrameSet attribute), 108
 numFrames (TotalDepth.LIS.core.Rle.RLEItemType01 attribute), 113
 numFrames() (TotalDepth.LAS.core.LASRead.LASBase method), 118
 numFrames() (TotalDepth.LIS.core.Type01Plan.FrameSetPlan method), 115
 numLogPasses() (TotalDepth.LIS.core.FileIndexer.FileIndex method), 96
 NUMPY_DATA_TYPE (TotalDepth.LIS.core.FrameSet.FrameSet attribute), 108
 numSamples() (TotalDepth.LIS.core.FrameSet.FrameSet method), 108
 numSubChannels (TotalDepth.LIS.core.FrameSet.ChArTe attribute), 107
 numSubChannels() (TotalDepth.LIS.core.FrameSet.FrameSet method), 108
 numValues (TotalDepth.LIS.core.FrameSet.FrameSet attribute), 108
 numValues (TotalDepth.LIS.core.FrameSet.SuChArTe attribute), 107
 numValues() (TotalDepth.LIS.core.Rle.RLE method), 112
 numValues() (TotalDepth.LIS.core.Rle.RLEItem method), 112
 O
 offScale() (TotalDepth.util.plot.PRESCfg.LineTransBase method), 159

- opacity (TotalDepth.util.plot.Stroke.Stroke attribute), [133](#)
- opticalLogScale (TotalDepth.LIS.core.LogiRec.EntryBlockSet attribute), [95](#)
- opticalUnits() (in module TotalDepth.LIS.core.Units), [74](#)
- ORDS_REPLACE (in module TotalDepth.LIS.core.Mnem), [77](#)
- ORDS_WS (in module TotalDepth.LIS.core.Mnem), [77](#)
- outpChIDs() (TotalDepth.util.plot.PRESCfg.PresCfg method), [160](#)
- outpCurveIDs() (TotalDepth.util.plot.PRESCfg.PresCfg method), [160](#)
- outpMnemS() (TotalDepth.LIS.core.LogPass.LogPass method), [101](#)
- ## P
- packAndWrite() (TotalDepth.LIS.core.RawStream.RawStream method), [79](#)
- Pad (class in TotalDepth.util.plot.Coord), [131](#)
- pathSplit() (in module TotalDepth.util.HtmlUtils), [125](#)
- PATTERN_MAP (in module TotalDepth.util.plot.AREACfg), [146](#)
- PhysFilmCfg (class in TotalDepth.util.plot.FILMCfg), [150](#)
- PhysFilmCfgLISRead (class in TotalDepth.util.plot.FILMCfg), [150](#)
- PhysFilmCfgXMLRead (class in TotalDepth.util.plot.FILMCfgXML), [152](#)
- Physical Record, [173](#)
- PhysRecBase (class in TotalDepth.LIS.core.PhysRec), [85](#)
- PhysRecRead (class in TotalDepth.LIS.core.PhysRec), [86](#)
- PhysRecTail (class in TotalDepth.LIS.core.PhysRec), [86](#)
- PhysRecWrite (class in TotalDepth.LIS.core.PhysRec), [87](#)
- plI() (TotalDepth.util.XmlWrite.XmlStream method), [128](#)
- Plot (class in TotalDepth.util.plot.Plot), [169](#)
- plot() (TotalDepth.util.plot.LogHeader.APIHeaderBase method), [163](#)
- plotLogPassLAS() (TotalDepth.util.plot.Plot.Plot method), [170](#)
- plotLogPassLIS() (TotalDepth.util.plot.Plot.Plot method), [170](#)
- PlotReadLIS (class in TotalDepth.util.plot.Plot), [171](#)
- PlotReadXML (class in TotalDepth.util.plot.Plot), [171](#)
- PlotRecordSet (class in TotalDepth.LIS.core.FileIndexer), [98](#)
- PlotRoll (class in TotalDepth.util.plot.Plot), [167](#)
- plotSVG() (TotalDepth.util.plot.Track.Track method), [140](#)
- polyLinePt() (TotalDepth.util.plot.Plot.PlotRoll method), [169](#)
- pprintAll() (in module TotalDepth.util.plot.AREACfg), [146](#)
- pprintPattern() (in module TotalDepth.util.plot.AREACfg), [146](#)
- PR_ATTRIBUTE_BITS (in module TotalDepth.LIS.core.PhysRec), [84](#)
- PR_ATTRIBUTE_UNUSED_MASK (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_ATTRIBUTE_UNUSED_ONLY_MASK (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_ATTRIBUTE_UNUSED_RESERVED_MASK (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_CHECKSUM_BIT (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_CHECKSUM_UNDEFINED_BIT (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_FILE_NUMBER_BIT (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_MAX_LENGTH (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_OLD_CHECK_ERROR_BIT (in module TotalDepth.LIS.core.PhysRec), [84](#)
- PR_OLD_PARITY_ERROR_BIT (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_PREDECESSOR_ATTRIBUTE_BIT (in module TotalDepth.LIS.core.PhysRec), [84](#)
- PR_PRH_ATTR_FORMAT (in module TotalDepth.LIS.core.PhysRec), [84](#)
- PR_PRH_LEN_FORMAT (in module TotalDepth.LIS.core.PhysRec), [84](#)
- PR_PRH_LENGTH (in module TotalDepth.LIS.core.PhysRec), [84](#)
- PR_PRT_CHECKSUM_FORMAT (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_PRT_CHECKSUM_LEN (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_PRT_FILE_NUM_FORMAT (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_PRT_FILE_NUM_LEN (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_PRT_FILE_NUM_MAX (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_PRT_FILE_NUM_MIN (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_PRT_REC_NUM_FORMAT (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_PRT_REC_NUM_LEN (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_PRT_REC_NUM_MAX (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_PRT_REC_NUM_MIN (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_RECORD_NUMBER_BIT (in module TotalDepth.LIS.core.PhysRec), [85](#)
- PR_SUCCESSOR_ATTRIBUTE_BIT (in module TotalDepth.LIS.core.PhysRec), [84](#)
- PR_TYPE_BIT (in module TotalDepth.LIS.core.PhysRec), [85](#)

PresCfg (class in TotalDepth.util.plot.PRESCfg), 160
 PresCfgLISRead (class in TotalDepth.util.plot.PRESCfg), 161
 PresCfgXMLRead (class in TotalDepth.util.plot.PRESCfgXML), 162
 prevFileName (TotalDepth.LIS.core.LogiRec.LrFileHead attribute), 90
 prevReelName (TotalDepth.LIS.core.LogiRec.LrReelHead attribute), 91
 prevTapeName (TotalDepth.LIS.core.LogiRec.LrTapeHead attribute), 91
 prhAttr (TotalDepth.LIS.core.PhysRec.PhysRecTail attribute), 86
 pStr() (TotalDepth.LIS.core.EngVal.EngVal method), 77
 pStr() (TotalDepth.LIS.core.Mnem.Mnem method), 78
 Pt (class in TotalDepth.util.plot.Coord), 131

R

range() (TotalDepth.LIS.core.Rle.RLEItem method), 112
 rangeList() (TotalDepth.LIS.core.Rle.RLE method), 113
 rAttr (TotalDepth.util.plot.LogHeader.Static attribute), 162
 RawStream (class in TotalDepth.LIS.core.RawStream), 79
 RE_COMMENT (in module TotalDepth.LAS.core.LASRead), 116
 RE_LINE_FIELD_0 (in module TotalDepth.LAS.core.LASRead), 117
 RE_LINE_FIELD_1 (in module TotalDepth.LAS.core.LASRead), 117
 RE_LINE_FIELD_2 (in module TotalDepth.LAS.core.LASRead), 117
 RE_SECT_HEAD (in module TotalDepth.LAS.core.LASRead), 116
 read() (TotalDepth.LIS.core.LogiRec.LrFileHeadTail method), 90
 read() (TotalDepth.LIS.core.RawStream.RawStream method), 79
 read() (TotalDepth.LIS.core.TifMarker.TifMarkerRead method), 83
 read49() (in module TotalDepth.LIS.core.pRepCode), 71
 read49() (in module TotalDepth.LIS.core.RepCode), 69
 read50() (in module TotalDepth.LIS.core.pRepCode), 71
 read50() (in module TotalDepth.LIS.core.RepCode), 69
 read56() (in module TotalDepth.LIS.core.pRepCode), 71
 read56() (in module TotalDepth.LIS.core.RepCode), 69
 read66() (in module TotalDepth.LIS.core.pRepCode), 71
 read66() (in module TotalDepth.LIS.core.RepCode), 69
 read68() (in module TotalDepth.LIS.core.pRepCode), 71
 read68() (in module TotalDepth.LIS.core.RepCode), 69
 read70() (in module TotalDepth.LIS.core.pRepCode), 71
 read70() (in module TotalDepth.LIS.core.RepCode), 69
 read73() (in module TotalDepth.LIS.core.pRepCode), 71
 read73() (in module TotalDepth.LIS.core.RepCode), 69
 read77() (in module TotalDepth.LIS.core.pRepCode), 71
 read77() (in module TotalDepth.LIS.core.RepCode), 69
 read79() (in module TotalDepth.LIS.core.pRepCode), 71
 read79() (in module TotalDepth.LIS.core.RepCode), 69
 readAndUnpack() (TotalDepth.LIS.core.RawStream.RawStream method), 79
 readBytes() (in module TotalDepth.LIS.core.RepCode), 69
 readBytes130() (in module TotalDepth.LIS.core.RepCode), 69
 readBytes234() (in module TotalDepth.LIS.core.RepCode), 69
 readBytes49() (in module TotalDepth.LIS.core.RepCode), 69
 readBytes50() (in module TotalDepth.LIS.core.RepCode), 69
 readBytes56() (in module TotalDepth.LIS.core.RepCode), 69
 readBytes66() (in module TotalDepth.LIS.core.RepCode), 69
 readBytes68() (in module TotalDepth.LIS.core.RepCode), 69
 readBytes70() (in module TotalDepth.LIS.core.RepCode), 69
 readBytes73() (in module TotalDepth.LIS.core.RepCode), 69
 readBytes77() (in module TotalDepth.LIS.core.RepCode), 69
 readBytes79() (in module TotalDepth.LIS.core.RepCode), 70
 readDir() (TotalDepth.util.plot.FILMCfgXML.FilmCfgXMLRead method), 153
 readFromFile() (TotalDepth.LIS.core.LogiRec.EntryBlockSet method), 95
 readLrBytes() (TotalDepth.LIS.core.File.FileRead method), 80
 readLrBytes() (TotalDepth.LIS.core.PhysRec.PhysRecRead method), 86
 readRepCode() (in module TotalDepth.LIS.core.RepCode), 70
 realUnitName() (in module TotalDepth.LIS.core.Units), 74
 RECT_ATTRS_FINE (in module TotalDepth.util.plot.LogHeader), 163
 remove() (TotalDepth.util.DictTree.DictTree method), 120
 RepCode, 173
 repeat (TotalDepth.LIS.core.Rle.RLEItem attribute), 112
 reportError() (TotalDepth.LIS.core.TifMarker.TifMarkerBase method), 83
 Representation Code, 174
 reset() (TotalDepth.LIS.core.TifMarker.TifMarkerBase method), 83
 reset() (TotalDepth.LIS.core.TifMarker.TifMarkerRead

- method), 83
 - reset() (TotalDepth.util.plot.Plot.CurvePlotScaleSlotMap method), 166
 - retAllFILMDestS() (TotalDepth.util.plot.FILMCfg.FilmCfg method), 151
 - retAllFILMDestS() (TotalDepth.util.plot.FILMCfg.FilmCfgLISRead method), 152
 - retAllFILMDestS() (TotalDepth.util.plot.FILMCfgXML.FilmCfgXMLRead method), 153
 - retExtChIndexList() (TotalDepth.LIS.core.LogPass.LogPass method), 101
 - retFILMDest() (TotalDepth.util.plot.FILMCfg.FilmCfg method), 151
 - retFILMDest() (TotalDepth.util.plot.FILMCfg.FilmCfgLISRead method), 152
 - retFILMDest() (TotalDepth.util.plot.FILMCfgXML.FilmCfgXMLRead method), 153
 - retHeadPane() (TotalDepth.util.plot.Plot.PlotRoll method), 168
 - retHtmlFileLink() (in module TotalDepth.util.HtmlUtils), 125
 - retHtmlFileName() (in module TotalDepth.util.HtmlUtils), 125
 - retLegendPane() (TotalDepth.util.plot.Plot.PlotRoll method), 168
 - retLrFromFile() (TotalDepth.LIS.core.LogiRec.LrFactoryRead method), 96
 - retMainPane() (TotalDepth.util.plot.Plot.PlotRoll method), 168
 - retMainPaneStart() (TotalDepth.util.plot.Plot.PlotRoll method), 169
 - retRowByMnem() (TotalDepth.LIS.core.LogiRec.LrTable method), 93
 - retSVGAttrsFromStroke() (in module TotalDepth.util.plot.Stroke), 133
 - retTailPane() (TotalDepth.util.plot.Plot.PlotRoll method), 169
 - retUnitConvert() (in module TotalDepth.LIS.core.Units), 74
 - retUnitConvertCategory() (in module TotalDepth.LIS.core.Units), 74
 - rewind() (TotalDepth.LIS.core.File.FileRead method), 80
 - right (TotalDepth.util.plot.Track.Track attribute), 140
 - rightL (TotalDepth.util.plot.PRESCfg.LineTransBase attribute), 158
 - rightP (TotalDepth.util.plot.PRESCfg.TrackWidthData attribute), 160
 - RLE (class in TotalDepth.LIS.core.Rle), 112
 - rle (TotalDepth.LIS.core.LogPass.LogPass attribute), 102
 - RLEItem (class in TotalDepth.LIS.core.Rle), 112
 - RLEItemType01 (class in TotalDepth.LIS.core.Rle), 113
 - RLEType01 (class in TotalDepth.LIS.core.Rle), 113
 - rootNode() (TotalDepth.util.plot.FILMCfgXML.FilmCfgXMLRead method), 153
 - rowLabels() (TotalDepth.LIS.core.LogiRec.LrTable method), 93
 - rowMnems() (TotalDepth.LIS.core.LogiRec.LrTable method), 93
 - RP66, 174
- ## S
- samples() (TotalDepth.LIS.core.LogiRec.DatumSpecBlock method), 95
 - scale() (TotalDepth.util.plot.Coord.Dim method), 130
 - scale() (TotalDepth.util.plot.Coord.Pt method), 131
 - ScaleSliceCurve (class in TotalDepth.util.plot.Plot), 166
 - SECT_DESCRIPTION_MAP (in module TotalDepth.LAS.core.LASRead), 117
 - SECT_NAMES (in module TotalDepth.LAS.core.LASRead), 116
 - SECT_TYPES_WITH_DATA_LINES (in module TotalDepth.LAS.core.LASRead), 116
 - SECT_TYPES_WITH_INDEX (in module TotalDepth.LAS.core.LASRead), 116
 - SectLine (class in TotalDepth.LAS.core.LASRead), 117
 - seek() (TotalDepth.LIS.core.RawStream.RawStream method), 79
 - seekCurrentLrStart() (TotalDepth.LIS.core.File.FileRead method), 80
 - seekCurrentLrStart() (TotalDepth.LIS.core.PhysRec.PhysRecRead method), 86
 - seekLr() (TotalDepth.LIS.core.File.FileRead method), 80
 - seekLr() (TotalDepth.LIS.core.PhysRec.PhysRecRead method), 86
 - setColRowSpan() (TotalDepth.util.DictTree.DictTreeHtmlTable method), 121
 - setEntryBlock() (TotalDepth.LIS.core.LogiRec.EntryBlockSet method), 95
 - setFrameBytes() (TotalDepth.LIS.core.FrameSet.FrameSet method), 109
 - setFrameSet() (TotalDepth.LIS.core.LogPass.LogPass method), 102
 - setFrameSetChX() (TotalDepth.LIS.core.LogPass.LogPass method), 102
 - setIndirectX() (TotalDepth.LIS.core.FrameSet.FrameSet method), 109
 - setLogicalRecord() (TotalDepth.LIS.core.FileIndexer.IndexLrFull method), 97
 - setLogicalRecord() (TotalDepth.LIS.core.FileIndexer.IndexObjBase method), 97

method), 98

setLogicalRecord() (TotalDepth.LIS.core.FileIndexer.IndexTable method), 98

setLogicalRecord() (TotalDepth.LIS.core.FileIndexer.IndexUnknownInternalFormat method), 98

setValue() (TotalDepth.LIS.core.LogiRec.CbEngVal method), 92

size (TotalDepth.util.plot.LogHeader.Static attribute), 163

size() (TotalDepth.util.plot.LogHeader.APIHeaderBase method), 163

skipLrBytes() (TotalDepth.LIS.core.File.FileRead method), 80

skipLrBytes() (TotalDepth.LIS.core.PhysRec.PhysRecRead method), 86

skipToEndOfFrame() (TotalDepth.LIS.core.Type01Plan.FrameSetPlan method), 115

skipToNextLr() (TotalDepth.LIS.core.File.FileRead method), 80

skipToNextLr() (TotalDepth.LIS.core.PhysRec.PhysRecRead method), 86

slice (TotalDepth.util.plot.Plot.ScaleSliceCurve attribute), 166

sliceDefaults() (in module TotalDepth.LIS.core.FrameSet), 107

span (TotalDepth.util.plot.Plot.ScaleSliceCurve attribute), 166

STANDARD_PAPER_DEPTH (in module TotalDepth.util.plot.PlotConstants), 136

STANDARD_PAPER_MARGIN (in module TotalDepth.util.plot.PlotConstants), 136

STANDARD_PAPER_WIDTH (in module TotalDepth.util.plot.PlotConstants), 136

start (TotalDepth.util.plot.Plot.ScaleSliceCurve attribute), 166

startNewRow() (TotalDepth.LIS.core.LogiRec.LrTable method), 93

startNewTimer() (TotalDepth.util.ExecTimer.ExecTimerList method), 123

Static (class in TotalDepth.util.plot.LogHeader), 162

status (TotalDepth.LIS.core.LogiRec.CbEngVal attribute), 92

step() (TotalDepth.util.FileBuffer.FileBuffer method), 124

stop() (TotalDepth.util.ExecTimer.ExecEvent method), 123

stopTimer() (TotalDepth.util.ExecTimer.ExecTimerList method), 123

str() (TotalDepth.util.plot.XMLCf.LgXMLBase method), 142

stream (TotalDepth.LIS.core.RawStream.RawStream attribute), 79

strFormat() (TotalDepth.LIS.core.EngVal.EngVal method), 77

strHeader() (TotalDepth.LIS.core.PhysRec.PhysRecBase method), 86

strHeader() (TotalDepth.LIS.core.TifMarker.TifMarkerBase method), 83

stride (TotalDepth.LIS.core.Rle.RLEItem attribute), 112

Stroke (class in TotalDepth.util.plot.Stroke), 133

StrokeBlackSolid (in module TotalDepth.util.plot.Stroke), 133

StrokeGreySolid (in module TotalDepth.util.plot.XGrid), 141

strRep() (TotalDepth.util.Histogram.Histogram method), 124

STRUCT_COMPONENT_BLOCK_PREAMBLE (in module TotalDepth.LIS.core.LogiRec), 89

STRUCT_DSB (in module TotalDepth.LIS.core.LogiRec), 89

STRUCT_ENTRY_BLOCK_PREAMBLE (in module TotalDepth.LIS.core.LogiRec), 89

STRUCT_LR_FILE_HEAD_TAIL (in module TotalDepth.LIS.core.LogiRec), 89

STRUCT_LR_HEAD (in module TotalDepth.LIS.core.LogiRec), 89

STRUCT_LR_REEL_TAPE_HEAD_TAIL (in module TotalDepth.LIS.core.LogiRec), 89

subChMnem() (TotalDepth.LIS.core.LogiRec.DatumSpecBlock method), 95

subChOffsRange() (TotalDepth.LIS.core.FrameSet.ChArTe method), 107

subChOffsSlice() (TotalDepth.LIS.core.FrameSet.ChArTe method), 107

SuChArTe (class in TotalDepth.LIS.core.FrameSet), 107

supportedFilmTracks() (TotalDepth.util.plot.FILMCfg.PhysFilmCfgLISRead method), 151

SVGCircle (class in TotalDepth.util.plot.SVGWriter), 133

SVGEllipse (class in TotalDepth.util.plot.SVGWriter), 133

SVGGroup (class in TotalDepth.util.plot.SVGWriter), 133

SVGLine (class in TotalDepth.util.plot.SVGWriter), 134

SVGPointList (class in TotalDepth.util.plot.SVGWriter), 134

SVGPolygon (class in TotalDepth.util.plot.SVGWriter), 134

SVGPolyline (class in TotalDepth.util.plot.SVGWriter), 134

SVGRect (class in TotalDepth.util.plot.SVGWriter), 134

SVGText (class in TotalDepth.util.plot.SVGWriter), 135

T

- TableRow (class in TotalDepth.LIS.core.LogiRec), 92
- tAttr (TotalDepth.util.plot.LogHeader.Static attribute), 163
- tell (TotalDepth.LIS.core.FileIndexer.IndexObjBase attribute), 98
- tell() (TotalDepth.LIS.core.File.FileRead method), 80
- tell() (TotalDepth.LIS.core.PhysRec.PhysRecRead method), 86
- tell() (TotalDepth.LIS.core.RawStream.RawStream method), 79
- tell() (TotalDepth.util.FileBuffer.FileBuffer method), 124
- tellLr() (TotalDepth.LIS.core.File.FileRead method), 80
- tellLr() (TotalDepth.LIS.core.PhysRec.PhysRecRead method), 86
- tellLrForFrame() (TotalDepth.LIS.core.Rle.RLEItemType01 method), 113
- tellLrForFrame() (TotalDepth.LIS.core.Rle.RLEType01 method), 114
- tExec (TotalDepth.util.ExecTimer.ExecEvent attribute), 123
- text (TotalDepth.util.plot.LogHeader.Static attribute), 163
- TEXT_ATTRS_FINE (in module TotalDepth.util.plot.LogHeader), 163
- TEXT_ATTRS_LARGE (in module TotalDepth.util.plot.LogHeader), 163
- TEXT_ATTRS_LARGE_WOB (in module TotalDepth.util.plot.LogHeader), 163
- TIF_FIRST_WORD_LIMIT (in module TotalDepth.LIS.core.TifMarker), 82
- TIF_NUM_WORDS (in module TotalDepth.LIS.core.TifMarker), 82
- TIF_TOTAL_BYTES (in module TotalDepth.LIS.core.TifMarker), 82
- TIF_WORD_ALL_FORMAT (in module TotalDepth.LIS.core.TifMarker), 82
- TIF_WORD_ALL_FORMAT_WRONG_SEX (in module TotalDepth.LIS.core.TifMarker), 82
- TIF_WORD_BYTES (in module TotalDepth.LIS.core.TifMarker), 82
- TIF_WORD_FORMAT (in module TotalDepth.LIS.core.TifMarker), 82
- TIF_WORD_FORMAT_WRONG_SEX (in module TotalDepth.LIS.core.TifMarker), 83
- TifMarkerBase (class in TotalDepth.LIS.core.TifMarker), 83
- TifMarkerRead (class in TotalDepth.LIS.core.TifMarker), 83
- TifMarkerWrite (class in TotalDepth.LIS.core.TifMarker), 83
- timer (TotalDepth.util.ExecTimer.ExecTimerList attribute), 123
- TITLE_FONT_FAMILY (TotalDepth.util.plot.Plot.Plot attribute), 169
- TITLE_FONT_SIZE (TotalDepth.util.plot.Plot.Plot attribute), 169
- to49() (in module TotalDepth.LIS.core.pRepCode), 71
- to50() (in module TotalDepth.LIS.core.pRepCode), 72
- to56() (in module TotalDepth.LIS.core.pRepCode), 72
- to66() (in module TotalDepth.LIS.core.pRepCode), 72
- to68() (in module TotalDepth.LIS.core.pRepCode), 72
- to70() (in module TotalDepth.LIS.core.pRepCode), 72
- to73() (in module TotalDepth.LIS.core.pRepCode), 72
- to77() (in module TotalDepth.LIS.core.pRepCode), 72
- to79() (in module TotalDepth.LIS.core.pRepCode), 72
- tocStr() (TotalDepth.LIS.core.FileIndexer.IndexFileHeadTail method), 97
- tocStr() (TotalDepth.LIS.core.FileIndexer.IndexLogPass method), 97
- tocStr() (TotalDepth.LIS.core.FileIndexer.IndexObjBase method), 98
- tocStr() (TotalDepth.LIS.core.FileIndexer.IndexReelHeadTail method), 98
- tocStr() (TotalDepth.LIS.core.FileIndexer.IndexTable method), 98
- tocStr() (TotalDepth.LIS.core.FileIndexer.IndexTapeHeadTail method), 98
- TotalDepth.LAS.core.LASRead (module), 116
- TotalDepth.LIS.core.cRepCode (module), 72
- TotalDepth.LIS.core.EngVal (module), 75
- TotalDepth.LIS.core.File (module), 80
- TotalDepth.LIS.core.FileIndexer (module), 96
- TotalDepth.LIS.core.FrameSet (module), 106
- TotalDepth.LIS.core.LogiRec (module), 87
- TotalDepth.LIS.core.LogPass (module), 100
- TotalDepth.LIS.core.Mnem (module), 77
- TotalDepth.LIS.core.PhysRec (module), 84
- TotalDepth.LIS.core.pRepCode (module), 70
- TotalDepth.LIS.core.RawStream (module), 78
- TotalDepth.LIS.core.RepCode (module), 68
- TotalDepth.LIS.core.Rle (module), 111
- TotalDepth.LIS.core.TifMarker (module), 81
- TotalDepth.LIS.core.Type01Plan (module), 114
- TotalDepth.LIS.core.Units (module), 73
- TotalDepth.util.CmnCmdOpts (module), 119
- TotalDepth.util.DictTree (module), 120
- TotalDepth.util.DirWalk (module), 122
- TotalDepth.util.ExecTimer (module), 122
- TotalDepth.util.FileBuffer (module), 123
- TotalDepth.util.Histogram (module), 124
- TotalDepth.util.HtmlUtils (module), 125
- TotalDepth.util.plot.AREACfg (module), 142
- TotalDepth.util.plot.Coord (module), 130
- TotalDepth.util.plot.FILMCfg (module), 146
- TotalDepth.util.plot.FILMCfgXML (module), 152
- TotalDepth.util.plot.LogHeader (module), 162
- TotalDepth.util.plot.Plot (module), 164
- TotalDepth.util.plot.PlotConstants (module), 136

TotalDepth.util.plot.PRESCfg (module), 153
 TotalDepth.util.plot.PRESCfgXML (module), 161
 TotalDepth.util.plot.Stroke (module), 133
 TotalDepth.util.plot.SVGWriter (module), 133
 TotalDepth.util.plot.Track (module), 137
 TotalDepth.util.plot.XGrid (module), 140
 TotalDepth.util.plot.XMLCfg (module), 141
 TotalDepth.util.plot.XMLMatches (module), 142
 TotalDepth.util.XmlWrite (module), 126
 totalFrames (TotalDepth.LIS.core.LogPass.LogPass attribute), 102
 totalFrames() (TotalDepth.LIS.core.Rle.RLEItemType01 method), 113
 totalFrames() (TotalDepth.LIS.core.Rle.RLEType01 method), 114
 TRAC_STANDARD_SPAN (TotalDepth.util.plot.FILMCfgXML.PhysFilmCfgXMLRead attribute), 152
 TRAC_UNIQUEID_TO_NON_STANDARD_SPAN (TotalDepth.util.plot.FILMCfgXML.PhysFilmCfgXMLRead attribute), 152
 TRAC_UNIQUEID_TO_NON_STANDARD_START (TotalDepth.util.plot.FILMCfgXML.PhysFilmCfgXMLRead attribute), 152
 TRAC_XML_UNIQUEID_TO_PRES (TotalDepth.util.plot.PRESCfgXML.CurveCfgXMLRead attribute), 161
 Track (class in TotalDepth.util.plot.Track), 140
 trackTopLeft (TotalDepth.util.plot.Plot.PlotRoll attribute), 168
 TrackWidthData (class in TotalDepth.util.plot.PRESCfg), 159
 tracValueFunction() (TotalDepth.util.plot.PRESCfg.CurveCfg method), 160
 tracWidthData() (TotalDepth.util.plot.PRESCfg.CurveCfg method), 160
 type01Plan (TotalDepth.LIS.core.LogPass.LogPass attribute), 102

U

uniqueIdS() (TotalDepth.util.plot.FILMCfgXML.FilmCfgXMLRead method), 153
 unit (TotalDepth.LAS.core.LASRead.SectLine attribute), 117
 UNIT_MAP (in module TotalDepth.util.plot.Coord), 130
 unitCategories() (in module TotalDepth.LIS.core.Units), 74
 UnitConvert (class in TotalDepth.LIS.core.Units), 73
 UnitConvertCategory (class in TotalDepth.LIS.core.Units), 73
 unitConvertor() (TotalDepth.LIS.core.Units.UnitConvertCategory method), 74
 unitDescription() (in module TotalDepth.LIS.core.Units), 74
 units() (in module TotalDepth.LIS.core.Units), 74
 units() (in module TotalDepth.util.plot.Coord), 130
 unitS() (TotalDepth.LAS.core.LASRead.LASSection method), 118
 units() (TotalDepth.LIS.core.Units.UnitConvertCategory method), 74
 UNITS_LAS_TO_LIS (TotalDepth.LAS.core.LASRead.LASBase attribute), 118
 unpack() (TotalDepth.LIS.core.File.FileRead method), 81
 UOM, 174
 usesOutpChannel() (TotalDepth.util.plot.PRESCfg.PresCfg method), 160
 valu (TotalDepth.LAS.core.LASRead.SectLine attribute), 17
 value (TotalDepth.LIS.core.LogiRec.CbEngVal attribute), 92
 value (TotalDepth.LIS.core.LogiRec.LrTable attribute), 93
 value (TotalDepth.LIS.core.LogiRec.TableRow attribute), 93
 value() (TotalDepth.LIS.core.FrameSet.AccActivity method), 111
 value() (TotalDepth.LIS.core.FrameSet.AccBias method), 111
 value() (TotalDepth.LIS.core.FrameSet.AccCount method), 110
 value() (TotalDepth.LIS.core.FrameSet.AccDelta method), 110
 value() (TotalDepth.LIS.core.FrameSet.AccDrift method), 111
 value() (TotalDepth.LIS.core.FrameSet.AccMax method), 110
 value() (TotalDepth.LIS.core.FrameSet.AccMean method), 110
 value() (TotalDepth.LIS.core.FrameSet.AccMin method), 110
 value() (TotalDepth.LIS.core.FrameSet.AccStDev method), 110
 value() (TotalDepth.LIS.core.FrameSet.FrameSet method), 109
 value() (TotalDepth.LIS.core.Rle.RLE method), 113
 value() (TotalDepth.LIS.core.Rle.RLEItem method), 112
 value() (TotalDepth.LIS.core.Rle.RLEItemType01 method), 113
 value() (TotalDepth.util.DictTree.DictTree method), 120
 valueIdxInFrame() (TotalDepth.LIS.core.FrameSet.FrameSet method), 109

valueIdxStartExtCh() (TotalDepth.LIS.core.FrameSet.FrameSet method), 109

values() (TotalDepth.LIS.core.LogiRec.DatumSpecBlock method), 95

values() (TotalDepth.LIS.core.Rle.RLE method), 113

values() (TotalDepth.LIS.core.Rle.RLEItem method), 112

values() (TotalDepth.LIS.core.Rle.RLEItemType01 method), 113

values() (TotalDepth.util.DictTree.DictTree method), 120

valuesPerFrame (TotalDepth.LIS.core.FrameSet.FrameSet attribute), 108

VIEW_BOX_UNITS_PER_PLOT_UNITS (in module TotalDepth.util.plot.PlotConstants), 136

viewBox (TotalDepth.util.plot.Plot.PlotRoll attribute), 168

viewPort() (TotalDepth.util.plot.LogHeader.APIHeaderBase method), 163

W

w (TotalDepth.util.plot.LogHeader.Static attribute), 163

width (TotalDepth.util.plot.Plot.PlotRoll attribute), 168

width (TotalDepth.util.plot.Stroke.Stroke attribute), 133

widthDim (TotalDepth.util.plot.Plot.PlotRoll attribute), 168

wordLength() (in module TotalDepth.LIS.core.pRepCode), 72

wrapPos() (TotalDepth.util.plot.PRESCfg.LineTransBase method), 158

wrapPos() (TotalDepth.util.plot.PRESCfg.LineTransLin method), 159

wrapPos() (TotalDepth.util.plot.PRESCfg.LineTransLog10 method), 159

write() (TotalDepth.LIS.core.File.FileWrite method), 81

write() (TotalDepth.LIS.core.RawStream.RawStream method), 79

write() (TotalDepth.LIS.core.TifMarker.TifMarkerWrite method), 83

writeBytes() (in module TotalDepth.LIS.core.RepCode), 70

writeBytes66() (in module TotalDepth.LIS.core.RepCode), 70

writeBytes68() (in module TotalDepth.LIS.core.RepCode), 70

writeBytes73() (in module TotalDepth.LIS.core.RepCode), 70

writeDictTreeAsTable() (in module TotalDepth.util.HtmlUtils), 126

writeECMAScript() (TotalDepth.util.XmlWrite.XmlStream method), 128

writeFileListAsTable() (in module TotalDepth.util.HtmlUtils), 125

writeFileListTrippleAsTable() (in module TotalDepth.util.HtmlUtils), 125

writeFilePathsAsTable() (in module TotalDepth.util.HtmlUtils), 126

writeHtmlFileAnchor() (in module TotalDepth.util.HtmlUtils), 125

writeHtmlFileLink() (in module TotalDepth.util.HtmlUtils), 125

writeLr() (TotalDepth.LIS.core.PhysRec.PhysRecWrite method), 87

writeToStderr() (TotalDepth.util.ExecTimer.ExecEvent method), 123

writeToStderr() (TotalDepth.util.ExecTimer.ExecTimerList method), 123

writeToStream() (TotalDepth.util.ExecTimer.ExecEvent method), 123

writeToStream() (TotalDepth.util.ExecTimer.ExecTimerList method), 123

X

x (TotalDepth.util.plot.LogHeader.Static attribute), 163

X Axis, 174

Xaxis, 174

xAxisDecl (TotalDepth.LIS.core.FrameSet.FrameSet attribute), 108

xAxisFirst() (TotalDepth.LIS.core.Rle.RLEItemType01 method), 113

xAxisFirst() (TotalDepth.LIS.core.Rle.RLEType01 method), 114

xAxisFirstEngVal (TotalDepth.LIS.core.LogPass.LogPass attribute), 102

xAxisFirstVal (TotalDepth.LIS.core.LogPass.LogPass attribute), 102

xAxisFirstValOptical (TotalDepth.LIS.core.LogPass.LogPass attribute), 102

xAxisIndex (TotalDepth.LIS.core.LogPass.LogPass attribute), 102

xAxisLast() (TotalDepth.LIS.core.Rle.RLEItemType01 method), 113

xAxisLast() (TotalDepth.LIS.core.Rle.RLEType01 method), 114

xAxisLastEngVal (TotalDepth.LIS.core.LogPass.LogPass attribute), 102

xAxisLastFrame() (TotalDepth.LIS.core.Rle.RLEType01 method), 114

xAxisLastVal (TotalDepth.LIS.core.LogPass.LogPass attribute), 102

xAxisLastValOptical (TotalDepth.LIS.core.LogPass.LogPass attribute), 102

xAxisSpacing (TotalDepth.LIS.core.LogPass.LogPass attribute), 102

[xAxisSpacingOptical](#) (TotalDepth.LIS.core.LogPass.LogPass attribute), [102](#)
[xAxisStart](#) (TotalDepth.LAS.core.LASRead.LASBase attribute), [118](#)
[xAxisStep](#) (TotalDepth.LAS.core.LASRead.LASBase attribute), [118](#)
[xAxisStep\(\)](#) (TotalDepth.LIS.core.FrameSet.FrameSet method), [108](#)
[xAxisStop](#) (TotalDepth.LAS.core.LASRead.LASBase attribute), [118](#)
[xAxisUnits](#) (TotalDepth.LAS.core.LASRead.LASBase attribute), [118](#)
[xAxisUnits](#) (TotalDepth.LIS.core.LogPass.LogPass attribute), [102](#)
[xAxisUnits](#) (TotalDepth.LIS.core.Rle.RLEType01 attribute), [114](#)
[xAxisUnitsOptical](#) (TotalDepth.LIS.core.LogPass.LogPass attribute), [102](#)
[xAxisValue\(\)](#) (TotalDepth.LIS.core.FrameSet.FrameSet method), [108](#)
[xDepth\(\)](#) (TotalDepth.util.plot.Plot.PlotRoll method), [169](#)
[XGrid](#) (class in TotalDepth.util.plot.XGrid), [141](#)
[xInc](#) (TotalDepth.LIS.core.LogiRec.EntryBlockSet attribute), [94](#)
[XML_CODI_MAP](#) (in module TotalDepth.util.plot.PRESCfgXML), [161](#)
[xmlSpacePreserve\(\)](#) (TotalDepth.util.XmlWrite.XmlStream method), [127](#)
[XmlStream](#) (class in TotalDepth.util.XmlWrite), [127](#)
[xMnem](#) (TotalDepth.util.plot.LogHeader.Static attribute), [163](#)
[xScale](#) (TotalDepth.util.plot.FILMCfg.PhysFilmCfg attribute), [150](#)
[xScale\(\)](#) (TotalDepth.util.plot.Plot.Plot method), [170](#)

Y

[y](#) (TotalDepth.util.plot.LogHeader.Static attribute), [163](#)
[ymd](#) (TotalDepth.LIS.core.LogiRec.LrWithDateField attribute), [90](#)

Z

[zeroBaseUnitsBox\(\)](#) (in module TotalDepth.util.plot.Coord), [131](#)
[zeroBaseUnitsDim\(\)](#) (in module TotalDepth.util.plot.Coord), [131](#)
[zeroBaseUnitsPad\(\)](#) (in module TotalDepth.util.plot.Coord), [131](#)
[zeroBaseUnitsPt\(\)](#) (in module TotalDepth.util.plot.Coord), [131](#)